Package 'mlr3torch'

September 12, 2024

Title Deep Learning with 'mlr3'

Version 0.1.1

Description Deep Learning library that extends the mlr3 framework by building upon the 'torch' package. It allows to conveniently build, train, and evaluate deep learning models without having to worry about low level details. Custom architectures can be created using the graph language defined in 'mlr3pipelines'.

License LGPL (>= 3)

BugReports https://github.com/mlr-org/mlr3torch/issues

URL https://mlr3torch.mlr-org.com/,
 https://github.com/mlr-org/mlr3torch/

Depends mlr3 (>= 0.20.0), mlr3pipelines (>= 0.6.0), torch (>= 0.13.0), R (>= 3.5.0)

Imports backports, checkmate (>= 2.2.0), data.table, lgr, methods, mlr3misc (>= 0.14.0), paradox (>= 1.0.0), R6, withr

Suggests callr, future, ggplot2, igraph, jsonlite, knitr, magick, mlr3tuning (>= 1.0.0), progress, rmarkdown, rpart, viridis, visNetwork, testthat (>= 3.0.0), torchyision (>= 0.6.0), waldo

Config/testthat/edition 3

NeedsCompilation no

ByteCompile no

Encoding UTF-8

RoxygenNote 7.3.2

Collate 'CallbackSet.R' 'zzz.R' 'TorchCallback.R'

'CallbackSetCheckpoint.R' 'CallbackSetEarlyStopping.R' 'CallbackSetHistory.R' 'CallbackSetProgress.R' 'ContextTorch.R' 'DataBackendLazy.R' 'utils.R' 'DataDescriptor.R'

'LearnerTorch.R' 'LearnerTorchFeatureless.R'

'LearnerTorchImage.R' 'LearnerTorchMLP.R' 'task_dataset.R'

'shape.R' 'PipeOpTorchIngress.R' 'LearnerTorchModel.R'

'LearnerTorchTabResNet.R' 'LearnerTorchVision.R'

2 Contents

'ModelDescriptor.R' 'PipeOpModule.R' 'PipeOpTorch.R'
'PipeOpTaskPreprocTorch.R' 'PipeOpTorchActivation.R'
'PipeOpTorchAvgPool.R' 'PipeOpTorchBatchNorm.R'
'PipeOpTorchBlock.R' 'PipeOpTorchCallbacks.R'
'PipeOpTorchConv.R' 'PipeOpTorchConvTranspose.R'
'PipeOpTorchDropout.R' 'PipeOpTorchHead.R'
'PipeOpTorchLayerNorm.R' 'PipeOpTorchLinear.R' 'TorchLoss.R'
'PipeOpTorchLoss.R' 'PipeOpTorchMaxPool.R' 'PipeOpTorchMerge.R'
'PipeOpTorchModel.R' 'PipeOpTorchOptimizer.R'
'PipeOpTorchReshape.R' 'PipeOpTorchSoftmax.R'
'TaskClassif_lazy_iris.R' 'TaskClassif_mnist.R'
'TaskClassif_tiny_imagenet.R' 'TorchDescriptor.R'
'TorchOptimizer.R' 'bibentries.R' 'cache.R' 'lazy_tensor.R'
'learner_torch_methods.R' 'materialize.R' 'merge_graphs.R'
'nn.R' 'nn_graph.R' 'paramset_torchlearner.R' 'preprocess.R'
'rd_info.R' 'with_torch_settings.R'
Author Sebastian Fischer [cre, aut] (https://orcid.org/0000-0002-9609-3197), Bernd Bischl [ctb] (https://orcid.org/0000-0001-6002-6980), Lukas Burk [ctb] (https://orcid.org/0000-0001-7528-3795), Martin Binder [aut],
Florian Pfisterer [ctb] (https://orcid.org/0000-0001-8867-762X)
Maintainer Sebastian Fischer <sebf.fischer@gmail.com></sebf.fischer@gmail.com>
Repository CRAN
Date/Publication 2024-09-12 14:30:02 UTC

Contents

ılr3torch-package	. 5
ssert_lazy_tensor	. 6
s_data_descriptor	. 7
s_lazy_tensor	. 8
s_torch_callback	. 9
s_torch_callbacks	. 10
s_torch_loss	. 10
s_torch_optimizer	. 11
ito_device	. 12
atchgetter_categ	. 12
atchgetter_num	. 13
allback_set	. 13
ataDescriptor	. 15
_lazy_tensor	. 17
zy_tensor	. 18
aterialize	. 18
ılr3torch_callbacks	. 20
llr3torch_losses	. 20
lr3torch_optimizers	. 21

Contents 3

mlr_backends_lazy	22
mlr_callback_set	
mlr_callback_set.checkpoint	
mlr_callback_set.history	
mlr_callback_set.progress	
mlr_context_torch	
mlr_learners.mlp	
nlr_learners.tab_resnet	
mlr_learners.torchvision	
mlr_learners.torch_featureless	
nlr_learners_torch	
nlr learners torch image	
nlr_learners_torch_model	
nlr_pipeops_augment_center_crop	
nlr_pipeops_augment_color_jitter	
nlr_pipeops_augment_crop	
nlr_pipeops_augment_hflip	
nlr_pipeops_augment_random_affine	
nlr_pipeops_augment_random_choice	
mlr_pipeops_augment_random_crop	
nlr_pipeops_augment_random_horizontal_flip	
nlr_pipeops_augment_random_order	
lr_pipeops_augment_random_resized_crop	
lr_pipeops_augment_random_vertical_flip	
llr_pipeops_augment_resized_crop	
nlr_pipeops_augment_rotate	
lr_pipeops_augment_vflip	
lr_pipeops_module	
lr_pipeops_nn_avg_pool1d	
nlr_pipeops_nn_avg_pool2d	
nlr_pipeops_nn_avg_pool3d	
nlr_pipeops_nn_batch_norm1d	
nlr_pipeops_nn_batch_norm2d	
nlr_pipeops_nn_batch_norm3d	
nlr_pipeops_nn_block	
nlr_pipeops_nn_celu	
nlr_pipeops_nn_conv1d	
alr pipeops nn conv2d	
nlr_pipeops_nn_conv3d	
nlr_pipeops_nn_conv_transpose1d	
mlr_pipeops_nn_conv_transpose2d	
nlr_pipeops_nn_conv_transpose3d	
nlr_pipeops_nn_dropout	
ni_pipeops_nn_elu	
ni_pipeops_nn_flatten	
nir_pipeops_nn_gelu	
nlr_pipeops_nn_glu	
nlr pipeops nn hardshrink	
HOLE THE BANKS THE HOLE SHIPE IN THE SECOND STATE OF THE SECOND ST	1(7.)

4 Contents

$mlr_pipeops_nn_hard sigmoid $. 105
$mlr_pipeops_nn_hardtanh \qquad \dots \qquad \dots \qquad \dots \qquad \dots \\$. 107
$mlr_pipeops_nn_head \dots \dots$	
$mlr_pipeops_nn_layer_norm \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	
$mlr_pipeops_nn_leaky_relu $	
$mlr_pipeops_nn_linear \ \dots $	
$mlr_pipeops_nn_log_sigmoid $	
mlr_pipeops_nn_max_pool1d	
mlr_pipeops_nn_max_pool2d	
mlr_pipeops_nn_max_pool3d	
mlr_pipeops_nn_merge	
mlr_pipeops_nn_merge_cat	
mlr_pipeops_nn_merge_prod	
mlr_pipeops_nn_merge_sum	
mlr_pipeops_nn_prelu	
mlr_pipeops_nn_relu	
mlr_pipeops_nn_relu6	
mlr_pipeops_nn_reshape	
mlr_pipeops_nn_rrelu	
mlr_pipeops_nn_selu	
mlr_pipeops_nn_sigmoid	
mlr_pipeops_nn_softmax	
mlr_pipeops_nn_softplus	
mlr_pipeops_nn_softshrink	
mlr_pipeops_nn_softsign	
mlr_pipeops_nn_squeeze	
mlr_pipeops_nn_tanh	
mlr_pipeops_nn_tanhshrink	
mlr_pipeops_nn_threshold	
mlr_pipeops_nn_unsqueeze	
mlr_pipeops_preproc_torch	
mlr_pipeops_torch_callbacks	
mlr_pipeops_torch_ingress	
mlr_pipeops_torch_ingress_categ	
mlr pipeops torch ingress ltnsr	
mlr_pipeops_torch_ingress_num	
mlr_pipeops_torch_loss	
mlr_pipeops_torch_model_classif	
mlr_pipeops_torch_model_regr	
mlr_pipeops_torch_optimizer	
mlr_pipeops_trafo_adjust_brightness	
mlr_pipeops_trafo_adjust_gamma	
mlr_pipeops_trafo_adjust_hue	
mlr_pipeops_trafo_adjust_saturation	
mlr_pipeops_trafo_grayscale	
mlr_pipeops_trafo_non	

mlr3torch-package 5

mlr_pipeops_trafo_normalize
mlr_pipeops_trafo_pad
mlr_pipeops_trafo_reshape
mlr_pipeops_trafo_resize
mlr_pipeops_trafo_rgb_to_grayscale
mlr_tasks_lazy_iris
mlr_tasks_mnist
mlr_tasks_tiny_imagenet
ModelDescriptor
model_descriptor_to_learner
model_descriptor_to_module
model_descriptor_union
nn
nn_graph
nn_merge_cat
nn_merge_prod
nn_merge_sum
nn_reshape
nn_squeeze
nn_unsqueeze
pipeop_preproc_torch
task_dataset
TorchCallback
TorchDescriptor
TorchIngressToken
TorchLoss
TorchOptimizer
torch_callback
t_clbk
t_loss
t_opt
228

mlr3torch-package

mlr3torch: Deep Learning with 'mlr3'

Description

Index

Deep Learning library that extends the mlr3 framework by building upon the 'torch' package. It allows to conveniently build, train, and evaluate deep learning models without having to worry about low level details. Custom architectures can be created using the graph language defined in 'mlr3pipelines'.

Options

• mlr3torch.cache: Whether to cache the downloaded data (TRUE) or not (FALSE, default). This can also be set to a specific folder on the file system to be used as the cache directory.

6 assert_lazy_tensor

Author(s)

Maintainer: Sebastian Fischer < sebf.fischer@gmail.com > (ORCID)

Authors:

• Martin Binder <mlr.developer@mb706.com>

Other contributors:

- Bernd Bischl

bernd_bischl@gmx.net> (ORCID) [contributor]
- Lukas Burk <github@quantenbrot.de> (ORCID) [contributor]
- Florian Pfisterer <pfistererf@googlemail.com> (ORCID) [contributor]

See Also

Useful links:

- https://mlr3torch.mlr-org.com/
- https://github.com/mlr-org/mlr3torch/
- Report bugs at https://github.com/mlr-org/mlr3torch/issues

assert_lazy_tensor

Assert Lazy Tensor

Description

Asserts whether something is a lazy tensor.

Usage

```
assert_lazy_tensor(x)
```

Arguments

x (any)

Object to check.

as_data_descriptor 7

as_data_descriptor

Convert to Data Descriptor

Description

Converts the input to a DataDescriptor.

Usage

```
as_data_descriptor(x, dataset_shapes, ...)
```

Arguments

```
x (any)
Object to convert.

dataset_shapes (named list() of (integer() or NULL))
The shapes of the output. Names are the elements of the list returned by the dataset. If the shape is not NULL (unknown, e.g. for images of different sizes) the first dimension must be NA to indicate the batch dimension.

... (any)
Further arguments passed to the DataDescriptor constructor.
```

Examples

```
ds = dataset("example",
   initialize = function() self$iris = iris[, -5],
   .getitem = function(i) list(x = torch_tensor(as.numeric(self$iris[i, ]))),
   .length = function() nrow(self$iris)
)()
as_data_descriptor(ds, list(x = c(NA, 4L)))

# if the dataset has a .getbatch method, the shapes are inferred
ds2 = dataset("example",
   initialize = function() self$iris = iris[, -5],
   .getbatch = function(i) list(x = torch_tensor(as.matrix(self$iris[i, ]))),
   .length = function() nrow(self$iris)
)()
as_data_descriptor(ds2)
```

8 as_lazy_tensor

as_lazy_tensor

Convert to Lazy Tensor

Description

Convert a object to a lazy_tensor.

Usage

```
as_lazy_tensor(x, ...)
## S3 method for class 'dataset'
as_lazy_tensor(x, dataset_shapes = NULL, ids = NULL, ...)
```

Arguments

```
x (any)
Object to convert to a lazy_tensor
... (any)
Additional arguments passed to the method.

dataset_shapes (named list() of (integer() or NULL))
The shapes of the output. Names are the elements of the list returned by the dataset. If the shape is not NULL (unknown, e.g. for images of different sizes) the first dimension must be NA to indicate the batch dimension.

ids (integer())
Which ids to include in the lazy tensor.
```

Examples

```
iris_ds = dataset("iris",
 initialize = function() {
   self$iris = iris[, -5]
 },
  .getbatch = function(i) {
   list(x = torch_tensor(as.matrix(self$iris[i, ])))
 },
  .length = function() nrow(self$iris)
)()
# no need to specify the dataset shapes as they can be inferred from the .getbatch method
# only first 5 observations
as_lazy_tensor(iris_ds, ids = 1:5)
# all observations
head(as_lazy_tensor(iris_ds))
iris_ds2 = dataset("iris",
 initialize = function() self$iris = iris[, -5],
  .getitem = function(i) list(x = torch_tensor(as.numeric(self$iris[i, ]))),
  .length = function() nrow(self$iris)
```

as_torch_callback 9

```
)()
# if .getitem is implemented we cannot infer the shapes as they might vary,
# so we have to annotate them explicitly
as_lazy_tensor(iris_ds2, dataset_shapes = list(x = c(NA, 4L)))[1:5]
# Convert a matrix
lt = as_lazy_tensor(matrix(rnorm(100), nrow = 20))
materialize(lt[1:5], rbind = TRUE)
```

as_torch_callback

Convert to a TorchCallback

Description

Converts an object to a TorchCallback.

Usage

```
as_torch_callback(x, clone = FALSE, ...)
```

Arguments

x (any)
Object to be converted.

clone (logical(1))
Whether to make a deep clone.

.. (any)

Additional arguments

Value

TorchCallback.

See Also

 $Other \ Callback: Torch Callback, as_torch_callbacks(), callback_set(), mlr3torch_callbacks, mlr_callback_set.mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch, t_clbk(), torch_callback()$

10 as_torch_loss

as_torch_callbacks

Convert to a list of Torch Callbacks

Description

Converts an object to a list of TorchCallback.

Usage

```
as_torch_callbacks(x, clone, ...)
```

Arguments

x (any)

Object to convert.

clone (logical(1))

Whether to create a deep clone.

... (any)

Additional arguments.

Value

```
list() of TorchCallbacks
```

See Also

 $Other Callback: TorchCallback, as_torch_callback(), callback_set(), mlr3torch_callbacks,\\ mlr_callback_set, mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch,\\ t_clbk(), torch_callback()$

 $Other\ Torch\ Descriptor:\ Torch\ Callback,\ Torch\ Descriptor,\ Torch\ Loss,\ Torch\ Optimizer,\ as_torch_loss(),\ as_torch_optimizer(),\ mlr\ 3torch_losses,\ mlr\ 3torch_optimizers,\ t_clbk(),\ t_loss(),\ t_opt()$

as_torch_loss

Convert to TorchLoss

Description

Converts an object to a TorchLoss.

Usage

```
as_torch_loss(x, clone = FALSE, ...)
```

as_torch_optimizer 11

Arguments

x (any)

Object to convert to a TorchLoss.

clone (logical(1))

Whether to make a deep clone.

... (any)

Additional arguments. Currently used to pass additional constructor arguments

to TorchLoss for objects of type nn_loss.

Value

TorchLoss.

See Also

Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(), t_loss(), t_opt()

as_torch_optimizer

Convert to TorchOptimizer

Description

Converts an object to a TorchOptimizer.

Usage

```
as_torch_optimizer(x, clone = FALSE, ...)
```

Arguments

x (any)

Object to convert to a TorchOptimizer.

clone (logical(1))

Whether to make a deep clone. Default is FALSE.

... (any)

Additional arguments. Currently used to pass additional constructor arguments

to TorchOptimizer for objects of type torch_optimizer_generator.

Value

TorchOptimizer

See Also

```
Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_loss(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(), t_loss(), t_opt()
```

12 batchgetter_categ

auto_device

Auto Device

Description

First tries cuda, then cpu.

Usage

```
auto_device(device = NULL)
```

Arguments

device (character(1))

The device. If not NULL, is returned as is.

batchgetter_categ

Batchgetter for Categorical data

Description

Converts a data frame of categorical data into a long tensor by converting the data to integers. No input checks are performed.

Usage

```
batchgetter_categ(data, device, ...)
```

Arguments

```
data (data.table)
```

data.table to be converted to a tensor.

device (character(1))

The device.

... (any)

Unused.

batchgetter_num 13

batchgetter_num	Batchgetter for Numeric Data	

Description

Converts a data frame of numeric data into a float tensor by calling as.matrix(). No input checks are performed

Usage

```
batchgetter_num(data, device, ...)
```

Arguments

```
data (data.table())
data.table to be converted to a tensor.

device (character(1))
The device on which the tensor should be created.
... (any)
Unused.
```

callback_set

Create a Set of Callbacks for Torch

Description

Creates an R6ClassGenerator inheriting from CallbackSet. Additionally performs checks such as that the stages are not accidentally misspelled. To create a TorchCallback use torch_callback().

In order for the resulting class to be cloneable, the private method \$deep_clone() must be provided.

Usage

```
callback_set(
  classname,
  on_begin = NULL,
  on_end = NULL,
  on_exit = NULL,
  on_epoch_begin = NULL,
  on_before_valid = NULL,
  on_epoch_end = NULL,
  on_batch_begin = NULL,
  on_batch_end = NULL,
  on_after_backward = NULL,
```

14 callback_set

```
on_batch_valid_begin = NULL,
on_batch_valid_end = NULL,
on_valid_end = NULL,
state_dict = NULL,
load_state_dict = NULL,
initialize = NULL,
public = NULL,
private = NULL,
private = NULL,
active = NULL,
parent_env = parent.frame(),
inherit = CallbackSet,
lock_objects = FALSE
```

Arguments

```
classname
                  (character(1))
                  The class name.
on_begin,
                  on end.
                                                           on_before_valid,
                                  on_epoch_begin,
on_epoch_end,
                  on_batch_begin,
                                      on_batch_end,
                                                         on_after_backward,
on_batch_valid_begin, on_batch_valid_end, on_valid_end, on_exit
                  (function)
                  Function to execute at the given stage, see section Stages.
state_dict
                  (function())
                  The function that retrieves the state dict from the callback. This is what will be
                  available in the learner after training.
load_state_dict
                  (function(state_dict))
                  Function that loads a callback state.
initialize
                  (function())
                  The initialization method of the callback.
public, private, active
                  (list())
                  Additional public, private, and active fields to add to the callback.
                  (environment())
parent_env
                  The parent environment for the R6Class.
inherit
                  (R6ClassGenerator)
                  From which class to inherit. This class must either be CallbackSet (default) or
                  inherit from it.
lock_objects
                  (logical(1))
                  Whether to lock the objects of the resulting R6Class. If FALSE (default), values
                  can be freely assigned to self without declaring them in the class definition.
```

Value

CallbackSet

DataDescriptor 15

See Also

Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), mlr3torch_callbacks, mlr_callback_set, mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch, t_clbk(), torch_callback()

DataDescriptor

Data Descriptor

Description

A data descriptor is a rather internal data structure used in the <code>lazy_tensor</code> data type. In essence it is an annotated <code>torch::dataset</code> and a preprocessing graph (consisting mosty of <code>PipeOpModule</code> operators). The additional meta data (e.g. pointer, shapes) allows to preprocess <code>lazy_tensors</code> in an <code>mlr3pipelines::Graph</code> just like any (non-lazy) data types. The preprocessing is applied when <code>materialize()</code> is called on the <code>lazy_tensor</code>.

To create a data descriptor, you can also use the as_data_descriptor() function.

Details

While it would be more natural to define this as an S3 class, we opted for an R6 class to avoid the usual trouble of serializing S3 objects. If each row contained a DataDescriptor as an S3 class, this would copy the object when serializing.

Public fields

```
dataset (torch::dataset)
    The dataset.
graph (Graph)
    The preprocessing graph.
dataset_shapes (named list() of (integer() or NULL))
    The shapes of the output.
input_map (character())
    The input map from the dataset to the preprocessing graph.
pointer (character(2))
    The output pointer.
pointer_shape (integer() | NULL)
    The shape of the output indicated by pointer.
dataset_hash (character(1))
    Hash for the wrapped dataset.
hash (character(1))
    Hash for the data descriptor.
graph_input (character())
     The input channels of the preprocessing graph (cached to save time).
pointer_shape_predict (integer() or NULL)
    Internal use only.
```

16 DataDescriptor

Methods

```
Public methods:
```

```
• DataDescriptor$new()
```

- DataDescriptor\$print()
- DataDescriptor\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
DataDescriptor$new(
  dataset,
  dataset_shapes = NULL,
  graph = NULL,
  input_map = NULL,
  pointer = NULL,
  pointer_shape = NULL,
  pointer_shape_predict = NULL,
  clone\_graph = TRUE
Arguments:
dataset (torch::dataset)
   The torch dataset. It should return a named list() of torch_tensor objects.
```

```
dataset_shapes (named list() of (integer() or NULL))
```

The shapes of the output. Names are the elements of the list returned by the dataset. If the shape is not NULL (unknown, e.g. for images of different sizes) the first dimension must be NA to indicate the batch dimension.

```
graph (Graph)
```

The preprocessing graph. If left NULL, no preprocessing is applied to the data and input_map, pointer, pointer_shape, and pointer_shape_predict are inferred in case the dataset returns only one element.

```
input_map (character())
```

Character vector that must have the same length as the input of the graph. Specifies how the data from the dataset is fed into the preprocessing graph.

```
pointer (character(2) | NULL)
```

Points to an output channel within graph: Element 1 is the PipeOp's id and element 2 is that PipeOp's output channel.

```
pointer_shape (integer() | NULL)
```

Shape of the output indicated by pointer.

```
pointer_shape_predict (integer() or NULL)
```

Internal use only. Used in a Graph to anticipate possible mismatches between train and predict shapes.

```
clone_graph (logical(1))
```

Whether to clone the preprocessing graph.

```
Method print(): Prints the object
```

Usage:

is_lazy_tensor 17

```
DataDescriptor$print(...)

Arguments:
... (any)
Unused
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
DataDescriptor$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

ModelDescriptor, lazy_tensor

Examples

```
# Create a dataset
ds = dataset(
   initialize = function() self$x = torch_randn(10, 3, 3),
   .getitem = function(i) list(x = self$x[i, ]),
   .length = function() nrow(self$x)
)()
dd = DataDescriptor$new(ds, list(x = c(NA, 3, 3)))
dd
# is the same as using the converter:
as_data_descriptor(ds, list(x = c(NA, 3, 3)))
```

 is_lazy_tensor

Check for lazy tensor

Description

Checks whether an object is a lazy tensor.

Usage

```
is_lazy_tensor(x)
```

Arguments

x (any)
Object to check.

18 materialize

lazy_tensor

Create a lazy tensor

Description

Create a lazy tensor.

Usage

```
lazy_tensor(data_descriptor = NULL, ids = NULL)
```

Arguments

```
data_descriptor

(DataDescriptor or NULL)

The data descriptor or NULL for a lazy tensor of length 0.

ids

(integer())

The elements of the data_descriptor to be included in the lazy tensor.
```

Examples

```
ds = dataset("example",
  initialize = function() self$iris = iris[, -5],
  .getitem = function(i) list(x = torch_tensor(as.numeric(self$iris[i, ]))),
  .length = function() nrow(self$iris)
)()
dd = as_data_descriptor(ds, list(x = c(NA, 4L)))
lt = as_lazy_tensor(dd)
```

materialize

Materialize Lazy Tensor Columns

Description

This will materialize a <code>lazy_tensor()</code> or a data.frame() / <code>list()</code> containing – among other things – <code>lazy_tensor()</code> columns. I.e. the data described in the underlying <code>DataDescriptors</code> is loaded for the indices in the <code>lazy_tensor()</code>, is preprocessed and then put unto the specified device. Because not all elements in a lazy tensor must have the same shape, a list of tensors is returned by default. If all elements have the same shape, these tensors can also be rbinded into a single tensor (parameter <code>rbind</code>).

Usage

```
materialize(x, device = "cpu", rbind = FALSE, ...)
## S3 method for class 'list'
materialize(x, device = "cpu", rbind = FALSE, cache = "auto", ...)
```

materialize 19

Arguments

Х	<pre>(any) The object to materialize. Either a lazy_tensor or a list() / data.frame() containing lazy_tensor columns.</pre>
device	(character(1)) The torch device.
rbind	(logical(1)) Whether to rbind the lazy tensor columns (TRUE) or return them as a list of tensors (FALSE). In the second case, there is no batch dimension.
•••	(any) Additional arguments.
cache	(character(1) or environment() or NULL) Optional cache for (intermediate) materialization results. Per default, caching will be enabled when the same dataset or data descriptor (with different output pointer) is used for more than one lazy tensor column.

Details

Materializing a lazy tensor consists of:

- 1. Loading the data from the internal dataset of the DataDescriptor.
- 2. Processing these batches in the preprocessing Graphs.
- 3. Returning the result of the PipeOp pointed to by the DataDescriptor (pointer).

With multiple lazy_tensor columns we can benefit from caching because: a) Output(s) from the dataset might be input to multiple graphs. b) Different lazy tensors might be outputs from the same graph.

For this reason it is possible to provide a cache environment. The hash key for a) is the hash of the indices and the dataset. The hash key for b) is the hash of the indices, dataset and preprocessing graph.

Value

```
(list() of lazy_tensors or a lazy_tensor)
```

Examples

```
lt1 = as_lazy_tensor(torch_randn(10, 3))
materialize(lt1, rbind = TRUE)
materialize(lt1, rbind = FALSE)
lt2 = as_lazy_tensor(torch_randn(10, 4))
d = data.table::data.table(lt1 = lt1, lt2 = lt2)
materialize(d, rbind = TRUE)
materialize(d, rbind = FALSE)
```

20 mlr3torch_losses

Description

A mlr3misc::Dictionary of torch callbacks. Use t_clbk() to conveniently retrieve callbacks. Can be converted to a data.table using as.data.table.

Usage

mlr3torch_callbacks

Format

An object of class DictionaryMlr3torchCallbacks (inherits from Dictionary, R6) of length 13.

See Also

```
Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), callback_set(), mlr_callback_set, mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch, t_clbk(), torch_callback()

Other Dictionary: mlr3torch_losses, mlr3torch_optimizers, t_opt()
```

Examples

```
mlr3torch_callbacks$get("checkpoint")
# is the same as
t_clbk("checkpoint")
# convert to a data.table
as.data.table(mlr3torch_callbacks)
```

mlr3torch_losses

Loss Functions

Description

Dictionary of torch loss descriptors. See t_loss() for conveniently retrieving a loss function. Can be converted to a data.table using as.data.table.

Usage

mlr3torch_losses

Format

An object of class DictionaryMlr3torchLosses (inherits from Dictionary, R6) of length 13.

mlr3torch_optimizers 21

Available Loss Functions

```
cross_entropy, 11, mse
```

See Also

```
Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_loss(), as_torch_optimizer(), mlr3torch_optimizers, t_clbk(), t_loss(), t_opt()

Other Dictionary: mlr3torch_callbacks, mlr3torch_optimizers, t_opt()
```

Examples

```
mlr3torch_losses$get("mse")
# is equivalent to
t_loss("mse")
# convert to a data.table
as.data.table(mlr3torch_losses)
```

```
mlr3torch_optimizers Optimizers
```

Description

Dictionary of torch optimizers. Use t_opt for conveniently retrieving optimizers. Can be converted to a data.table using as.data.table.

Usage

```
mlr3torch_optimizers
```

Format

An object of class DictionaryMlr3torchOptimizers (inherits from Dictionary, R6) of length 13.

Available Optimizers

```
adadelta, adagrad, adam, asgd, rmsprop, rprop, sgd
```

See Also

```
Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, t_clbk(), t_loss(), t_opt()

Other Dictionary: mlr3torch_callbacks, mlr3torch_losses, t_opt()
```

22 mlr_backends_lazy

Examples

```
mlr3torch_optimizers$get("adam")
# is equivalent to
t_opt("adam")
# convert to a data.table
as.data.table(mlr3torch_optimizers)
```

mlr_backends_lazy

Lazy Data Backend

Description

This lazy data backend wraps a constructor that lazily creates another backend, e.g. by downloading (and caching) some data from the internet. This backend should be used, when some metadata of the backend is known in advance and should be accessible before downloading the actual data. When the backend is first constructed, it is verified that the provided metadata was correct, otherwise an informative error message is thrown. After the construction of the lazily constructed backend, calls like \$data(), \$missings(), \$distinct(), or \$hash() are redirected to it.

Information that is available before the backend is constructed is:

- nrow The number of rows (set as the length of the rownames).
- ncol The number of columns (provided via the id column of col_info).
- colnames The column names.
- rownames The row names.
- col_info The column information, which can be obtained via mlr3::col_info().

Beware that accessing the backend's hash also contructs the backend.

Note that while in most cases the data contains lazy_tensor columns, this is not necessary and the naming of this class has nothing to do with the lazy_tensor data type.

Important

When the constructor generates factor() variables it is important that the ordering of the levels in data corresponds to the ordering of the levels in the col_info argument.

Super class

```
mlr3::DataBackend -> DataBackendLazy
```

Active bindings

```
backend (DataBackend)
     The wrapped backend that is lazily constructed when first accessed.
nrow (integer(1))
     Number of rows (observations).
```

mlr_backends_lazy 23

```
ncol (integer(1))
```

Number of columns (variables), including the primary key column.

rownames (integer())

Returns vector of all distinct row identifiers, i.e. the contents of the primary key column.

colnames (character())

Returns vector of all column names, including the primary key column.

is_constructed (logical(1))

Whether the backend has already been constructed.

Methods

Public methods:

- DataBackendLazy\$new()
- DataBackendLazy\$data()
- DataBackendLazy\$head()
- DataBackendLazy\$distinct()
- DataBackendLazy\$missings()
- DataBackendLazy\$print()

Method new(): Creates a new instance of this R6 class.

Usage:

DataBackendLazy\$new(constructor, rownames, col_info, primary_key, data_formats)

Arguments:

```
constructor (function)
```

A function with argument backend (the lazy backend), whose return value must be the actual backend. This function is called the first time the field \$backend is accessed.

```
rownames (integer())
```

The row names. Must be a permutation of the rownames of the lazily constructed backend. col_info (data.table::data.table())

A data.table with columns id, type and levels containing the column id, type and levels. Note that the levels must be provided in the correct order.

```
primary_key (character(1))
```

Name of the primary key column.

```
data_formats (character())
```

Set of supported data formats. E.g. "data.table". These must be a subset of the data formats of the lazily constructed backend.

Method data(): Returns a slice of the data in the specified format. The rows must be addressed as vector of primary key values, columns must be referred to via column names. Queries for rows with no matching row id and queries for columns with no matching column name are silently ignored. Rows are guaranteed to be returned in the same order as rows, columns may be returned in an arbitrary order. Duplicated row ids result in duplicated rows, duplicated column names lead to an exception.

Accessing the data triggers the construction of the backend.

Usage:

24 mlr_backends_lazy

```
DataBackendLazy$data(rows, cols, data_format = "data.table")
 Arguments:
 rows (integer())
     Row indices.
 cols (character())
     Column names.
 data_format (character(1))
     Desired data format, e.g. "data.table" or "Matrix".
Method head(): Retrieve the first n rows. This triggers the construction of the backend.
 Usage:
 DataBackendLazy$head(n = 6L)
 Arguments:
 n (integer(1))
     Number of rows.
 Returns: data.table::data.table() of the first n rows.
Method distinct(): Returns a named list of vectors of distinct values for each column spec-
ified. If na_rm is TRUE, missing values are removed from the returned vectors of distinct values.
Non-existing rows and columns are silently ignored.
This triggers the construction of the backend.
 Usage:
 DataBackendLazy$distinct(rows, cols, na_rm = TRUE)
 Arguments:
 rows (integer())
     Row indices.
 cols (character())
     Column names.
 na_rm (logical(1))
     Whether to remove NAs or not.
 Returns: Named list() of distinct values.
Method missings(): Returns the number of missing values per column in the specified slice of
data. Non-existing rows and columns are silently ignored.
This triggers the construction of the backend.
 Usage:
 DataBackendLazy$missings(rows, cols)
 Arguments:
 rows (integer())
     Row indices.
 cols (character())
     Column names.
 Returns: Total of missing values per column (named numeric()).
Method print(): Printer.
 Usage:
 DataBackendLazy$print()
```

mlr_callback_set 25

Examples

```
# We first define a backend constructor
constructor = function(backend) {
 cat("Data is constructed!\n")
 DataBackendDataTable$new(
   data.table(x = rnorm(10), y = rnorm(10), row_id = 1:10),
   primary_key = "row_id"
 )
}
# to wrap this backend constructor in a lazy backend, we need to provide the correct metadata for it
column_info = data.table(
 id = c("x", "y", "row_id"),
 type = c("numeric", "numeric", "integer"),
 levels = list(NULL, NULL, NULL)
backend_lazy = DataBackendLazy$new(
 constructor = constructor,
 rownames = 1:10,
 col_info = column_info,
 data_formats = "data.table",
 primary_key = "row_id"
# Note that the constructor is not called for the calls below
# as they can be read from the metadata
backend_lazy$nrow
backend_lazy$rownames
backend_lazy$ncol
backend_lazy$colnames
col_info(backend_lazy)
# Only now the backend is constructed
backend_lazy$data(1, "x")
# Is the same as:
backend_lazy$backend$data(1, "x")
```

mlr_callback_set

Base Class for Callbacks

Description

Base class from which callbacks should inherit (see section *Inheriting*). A callback set is a collection of functions that are executed at different stages of the training loop. They can be used to gain more control over the training process of a neural network without having to write everything from scratch.

When used a in torch learner, the CallbackSet is wrapped in a TorchCallback. The latters parameter set represents the arguments of the CallbackSet's \$initialize() method.

26 mlr_callback_set

Inheriting

For each available stage (see section *Stages*) a public method \$on_<stage>() can be defined. The evaluation context (a ContextTorch) can be accessed via self\$ctx, which contains the current state of the training loop. This context is assigned at the beginning of the training loop and removed afterwards. Different stages of a callback can communicate with each other by assigning values to \$self.

State: To be able to store information in the \$model slot of a LearnerTorch, callbacks support a state API. You can overload the \$state_dict() public method to define what will be stored in learner\$model\$callbacks\$<id> after training finishes. This then also requires to implement a \$load_state_dict(state_dict) method that defines how to load a previously saved callback state into a different callback. Note that the \$state_dict() should not include the parameter values that were used to initialize the callback.

For creating custom callbacks, the function torch_callback() is recommended, which creates a CallbackSet and then wraps it in a TorchCallback. To create a CallbackSet the convenience function callback_set() can be used. These functions perform checks such as that the stages are not accidentally misspelled.

Stages

- begin:: Run before the training loop begins.
- epoch_begin :: Run he beginning of each epoch.
- batch_begin :: Run before the forward call.
- after_backward :: Run after the backward call.
- batch_end :: Run after the optimizer step.
- batch_valid_begin :: Run before the forward call in the validation loop.
- batch_valid_end :: Run after the forward call in the validation loop.
- valid_end :: Run at the end of validation.
- epoch_end :: Run at the end of each epoch.
- end :: Run after last epoch.
- exit :: Run at last, using on.exit().

Terminate Training

If training is to be stopped, it is possible to set the field \$terminate of ContextTorch. At the end of every epoch this field is checked and if it is TRUE, training stops. This can for example be used to implement custom early stopping.

Public fields

```
ctx (ContextTorch or NULL)
```

The evaluation context for the callback. This field should always be NULL except during the \$train() call of the torch learner.

mlr_callback_set 27

Active bindings

```
stages (character())

The active stages of this callback set.
```

Methods

Public methods:

- CallbackSet\$print()
- CallbackSet\$state_dict()
- CallbackSet\$load_state_dict()
- CallbackSet\$clone()

```
Method print(): Prints the object.
```

```
Usage:
CallbackSet$print(...)
Arguments:
... (any)
    Currently unused.
```

Method state_dict(): Returns information that is kept in the the LearnerTorch's state after training. This information should be loadable into the callback using \$load_state_dict() to be able to continue training. This returns NULL by default.

```
Usage:
CallbackSet$state_dict()
```

Method load_state_dict(): Loads the state dict into the callback to continue training.

```
Usage:
CallbackSet$load_state_dict(state_dict)
Arguments:
state_dict (any)
    The state dict as retrieved via $state_dict().
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
CallbackSet$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), callback_set(), mlr3torch_callbacks, mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch, t_clbk(), torch_callback()
```

```
mlr_callback_set.checkpoint
```

Checkpoint Callback

Description

Saves the optimizer and network states during training. The final network and optimizer are always stored.

Details

Saving the learner itself in the callback with a trained model is impossible, as the model slot is set *after* the last callback step is executed.

Super class

```
mlr3torch::CallbackSet -> CallbackSetCheckpoint
```

Methods

Public methods:

- CallbackSetCheckpoint\$new()
- CallbackSetCheckpoint\$on_epoch_end()
- CallbackSetCheckpoint\$on_batch_end()
- CallbackSetCheckpoint\$on_exit()
- CallbackSetCheckpoint\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
CallbackSetCheckpoint$new(path, freq, freq_type = "epoch")
```

Arguments:

```
path (character(1))
```

The path to a folder where the models are saved.

```
freq (integer(1))
```

The frequency how often the model is saved. Frequency is either per step or epoch, which can be configured through the freq_type parameter.

```
freq_type (character(1))
```

Can be be either "epoch" (default) or "step".

Method on_epoch_end(): Saves the network and optimizer state dict. Does nothing if freq_type or freq are not met.

```
Usage:
```

```
CallbackSetCheckpoint$on_epoch_end()
```

Method on_batch_end(): Saves the selected objects defined in save. Does nothing if freq_type or freq are not met.

Usage:

CallbackSetCheckpoint\$on_batch_end()

Method on_exit(): Saves the learner.

Usage:

CallbackSetCheckpoint\$on_exit()

Method clone(): The objects of this class are cloneable with this method.

Usage:

CallbackSetCheckpoint\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), callback_set(), mlr3torch_callbacks, mlr_callback_set, mlr_callback_set.progress, mlr_context_torch, t_clbk(), torch_callback()

```
mlr_callback_set.history
```

History Callback

Description

Saves the training and validation history during training. The history is saved as a data.table in the \$train and \$valid slots. The first column is always epoch.

Super class

```
mlr3torch::CallbackSet -> CallbackSetHistory
```

Methods

Public methods:

- CallbackSetHistory\$on_begin()
- CallbackSetHistory\$state_dict()
- CallbackSetHistory\$load_state_dict()
- CallbackSetHistory\$on_before_valid()
- CallbackSetHistory\$on_epoch_end()
- CallbackSetHistory\$clone()

Method on_begin(): Initializes lists where the train and validation metrics are stored.

```
Usage:
 CallbackSetHistory$on_begin()
Method state_dict(): Converts the lists to data.tables.
 Usage:
 CallbackSetHistory$state_dict()
Method load_state_dict(): Sets the field $train and $valid to those contained in the state
dict.
 Usage:
 CallbackSetHistory$load_state_dict(state_dict)
 Arguments:
 state_dict (callback_state_history)
     The state dict as retrieved via $state_dict().
Method on_before_valid(): Add the latest training scores to the history.
 Usage:
 CallbackSetHistory$on_before_valid()
Method on_epoch_end(): Add the latest validation scores to the history.
 Usage:
 CallbackSetHistory$on_epoch_end()
Method clone(): The objects of this class are cloneable with this method.
 Usage:
 CallbackSetHistory$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

```
mlr_callback_set.progress
```

Progress Callback

Description

Prints a progress bar and the metrics for training and validation.

Super class

```
mlr3torch::CallbackSet -> CallbackSetProgress
```

Methods

```
Public methods:
```

```
• CallbackSetProgress$on_epoch_begin()
```

```
• CallbackSetProgress$on_batch_end()
```

- CallbackSetProgress\$on_before_valid()
- CallbackSetProgress\$on_batch_valid_end()
- CallbackSetProgress\$on_epoch_end()
- CallbackSetProgress\$clone()

```
Method on_epoch_begin(): Initializes the progress bar for training.
```

Usage:

CallbackSetProgress\$on_epoch_begin()

Method on_batch_end(): Increments the training progress bar.

Usage.

CallbackSetProgress\$on_batch_end()

Method on_before_valid(): Creates the progress bar for validation.

Usage:

CallbackSetProgress\$on_before_valid()

Method on_batch_valid_end(): Increments the validation progress bar.

Usage:

CallbackSetProgress\$on_batch_valid_end()

Method on_epoch_end(): Prints a summary of the training and validation process.

Usage:

CallbackSetProgress\$on_epoch_end()

Method clone(): The objects of this class are cloneable with this method.

Usage:

CallbackSetProgress\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), callback_set(), mlr3torch_callbacks, mlr_callback_set, mlr_callback_set.checkpoint, mlr_context_torch, t_clbk(), torch_callback()
```

32 mlr_context_torch

mlr_context_torch

Context for Torch Learner

Description

Context for training a torch learner. This is the - mostly read-only - information callbacks have access to through the argument ctx. For more information on callbacks, see CallbackSet.

Public fields

```
learner (Learner)
    The torch learner.
task_train (Task)
    The training task.
task_valid (Task or NULL)
    The validation task.
loader_train (torch::dataloader)
    The data loader for training.
loader_valid (torch::dataloader)
     The data loader for validation.
measures_train (list() of Measures)
    Measures used for training.
measures_valid (list() of Measures)
    Measures used for validation.
network (torch::nn_module)
    The torch network.
optimizer (torch::optimizer)
    The optimizer.
loss_fn (torch::nn_module)
    The loss function.
total_epochs (integer(1))
    The total number of epochs the learner is trained for.
last_scores_train (named list() or NULL)
    The scores from the last training batch. Names are the ids of the training measures. If
    LearnerTorch sets eval_freq different from 1, this is NULL in all epochs that don't eval-
     uate the model.
last_scores_valid (list())
    The scores from the last validation batch. Names are the ids of the validation measures. If
    LearnerTorch sets eval_freq different from 1, this is NULL in all epochs that don't evaluate
     the model.
epoch (integer(1))
    The current epoch.
```

33 mlr_context_torch

```
step (integer(1))
     The current iteration.
prediction_encoder (function())
     The learner's prediction encoder.
batch (named list() of torch_tensors)
     The current batch.
terminate (logical(1))
     If this field is set to TRUE at the end of an epoch, training stops.
```

Methods

Public methods:

- ContextTorch\$new()
- ContextTorch\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
ContextTorch$new(
  learner,
  task_train,
  task_valid = NULL,
  loader_train,
  loader_valid = NULL,
  measures_train = NULL,
  measures_valid = NULL,
  network,
  optimizer,
  loss_fn,
  total_epochs,
  prediction_encoder,
  eval\_freq = 1L
)
Arguments:
learner (Learner)
   The torch learner.
task_train (Task)
   The training task.
task_valid (Task or NULL)
   The validation task.
loader_train (torch::dataloader)
   The data loader for training.
loader_valid (torch::dataloader or NULL)
   The data loader for validation.
measures_train (list() of Measures or NULL)
   Measures used for training. Default is NULL.
```

34 mlr_learners.mlp

```
measures_valid (list() of Measures or NULL)
           Measures used for validation.
       network (torch::nn_module)
           The torch network.
       optimizer (torch::optimizer)
           The optimizer.
       loss_fn (torch::nn_module)
           The loss function.
       total_epochs (integer(1))
           The total number of epochs the learner is trained for.
       prediction_encoder (function())
           The learner's prediction encoder.
       eval_freq (integer(1))
           The evaluation frequency.
     Method clone(): The objects of this class are cloneable with this method.
       Usage:
       ContextTorch$clone(deep = FALSE)
       Arguments:
       deep Whether to make a deep clone.
See Also
    Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), callback_set(),
    mlr3torch_callbacks, mlr_callback_set, mlr_callback_set.checkpoint, mlr_callback_set.progress,
    t_clbk(), torch_callback()
```

mlr_learners.mlp

My Little Pony

Description

Fully connected feed forward network with dropout after each activation function. The features can either be a single <code>lazy_tensor</code> or one or more numeric columns (but not both).

Dictionary

This Learner can be instantiated using the sugar function lrn():

```
lrn("classif.mlp", ...)
lrn("regr.mlp", ...)
```

mlr_learners.mlp 35

Properties

```
Supported task types: 'classif', 'regr'
Predict Types:

classif: 'response', 'prob'
regr: 'response'

Feature Types: "integer", "numeric", "lazy_tensor"
Required Packages: mlr3, mlr3torch, torch
```

Parameters

Parameters from LearnerTorch, as well as:

- activation :: [nn_module]
 The activation function. Is initialized to nn_relu.
- activation_args :: named list()
 A named list with initialization arguments for the activation function. This is intialized to an empty list.
- neurons :: integer()
 The number of neurons per hidden layer. By default there is no hidden layer. Setting this to c(10, 20) would have a the first hidden layer with 10 neurons and the second with 20.
- p :: numeric(1)
 The dropout probability. Is initialized to 0.5.
- shape :: integer() or NULL

 The input shape of length 2, e.g. c(NA, 5). Only needs to be present when there is a lazy tensor input with unknown shape (NULL). Otherwise the input shape is inferred from the number of numeric features.

Super classes

```
mlr3::Learner -> mlr3torch::LearnerTorch -> LearnerTorchMLP
```

Methods

Public methods:

- LearnerTorchMLP\$new()
- LearnerTorchMLP\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
LearnerTorchMLP$new(
  task_type,
  optimizer = NULL,
  loss = NULL,
  callbacks = list()
)
```

36 mlr_learners.mlp

```
Arguments:
task_type (character(1))
    The task type, either "classif" or "regr".
optimizer (TorchOptimizer)
    The optimizer to use for training. Per default, adam is used.
loss (TorchLoss)
    The loss used to train the network. Per default, mse is used for regression and cross_entropy for classification.
callbacks (list() of TorchCallbacks)
    The callbacks. Must have unique ids.

Method clone(): The objects of this class are cloneable with this method.
Usage:
LearnerTorchMLP$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

 $Other\ Learner:\ mlr_learners.\ tab_resnet,\ mlr_learners.\ torch_featureless,\ mlr_learners_torch,\ mlr_learners_torch_model$

Examples

```
# Define the Learner and set parameter values
learner = lrn("classif.mlp")
learner$param_set$set_values(
   epochs = 1, batch_size = 16, device = "cpu",
   neurons = 10
)

# Define a Task
task = tsk("iris")

# Create train and test set
ids = partition(task)

# Train the learner on the training ids
learner$train(task, row_ids = ids$train)

# Make predictions for the test rows
predictions = learner$predict(task, row_ids = ids$test)

# Score the predictions
predictions$score()
```

```
mlr_learners.tab_resnet
```

Tabular ResNet

Description

Tabular resnet.

Dictionary

This Learner can be instantiated using the sugar function lrn():

```
lrn("classif.tab_resnet", ...)
lrn("regr.tab_resnet", ...)
```

Properties

- Supported task types: 'classif', 'regr'
- Predict Types:
 - classif: 'response', 'prob'
 - regr: 'response'
- Feature Types: "integer", "numeric"
- Required Packages: mlr3, mlr3torch, torch

Parameters

Parameters from LearnerTorch, as well as:

```
• n_blocks :: integer(1)
The number of blocks.
```

• d_block::integer(1)

The input and output dimension of a block.

d_hidden :: integer(1)
 The latent dimension of a block.

• d_hidden_multiplier :: integer(1)
Alternative way to specify the latent dimension as d_block * d_hidden_multiplier.

```
• dropout1:: numeric(1)
First dropout ratio.
```

• dropout2:: numeric(1) Second dropout ratio.

Super classes

```
mlr3::Learner -> mlr3torch::LearnerTorch -> LearnerTorchTabResNet
```

Methods

Public methods:

- LearnerTorchTabResNet\$new()
- LearnerTorchTabResNet\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
 LearnerTorchTabResNet$new(
    task_type,
    optimizer = NULL,
    loss = NULL,
    callbacks = list()
 Arguments:
 task_type (character(1))
     The task type, either "classif" or "regr".
 optimizer (TorchOptimizer)
     The optimizer to use for training. Per default, adam is used.
 loss (TorchLoss)
     The loss used to train the network. Per default, mse is used for regression and cross_entropy
     for classification.
 callbacks (list() of TorchCallbacks)
     The callbacks. Must have unique ids.
Method clone(): The objects of this class are cloneable with this method.
 LearnerTorchTabResNet$clone(deep = FALSE)
 Arguments:
```

References

Gorishniy Y, Rubachev I, Khrulkov V, Babenko A (2021). "Revisiting Deep Learning for Tabular Data." *arXiv*, **2106.11959**.

See Also

```
Other Learner: mlr_learners.mlp, mlr_learners.torch_featureless, mlr_learners_torch, mlr_learners_torch_image, mlr_learners_torch_model
```

Examples

```
# Define the Learner and set parameter values
learner = lrn("classif.tab_resnet")
learner$param_set$set_values(
  epochs = 1, batch_size = 16, device = "cpu",
```

deep Whether to make a deep clone.

mlr_learners.torchvision

```
n_blocks = 2, d_block = 10, d_hidden = 20, dropout1 = 0.3, dropout2 = 0.3
)

# Define a Task
task = tsk("iris")

# Create train and test set
ids = partition(task)

# Train the learner on the training ids
learner$train(task, row_ids = ids$train)

# Make predictions for the test rows
predictions = learner$predict(task, row_ids = ids$test)

# Score the predictions
predictions$core()
```

mlr_learners.torchvision

AlexNet Image Classifier

Description

Classic image classification networks from torchvision.

Parameters

Parameters from LearnerTorchImage and

pretrained :: logical(1)
 Whether to use the pretrained model. The final linear layer will be replaced with a new nn_linear with the number of classes inferred from the Task.

Properties

- Supported task types: "classif"
- Predict Types: "response" and "prob"
- Feature Types: "lazy_tensor"
- Required packages: "mlr3torch", "torch", "torchvision"

Super classes

mlr3::Learner->mlr3torch::LearnerTorch->mlr3torch::LearnerTorchVision

Methods

Public methods:

- LearnerTorchVision\$new()
- LearnerTorchVision\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
LearnerTorchVision$new(
    name,
    module_generator,
    label,
    optimizer = NULL,
    loss = NULL,
    callbacks = list()
)
Arguments:
name (character(1))
    The name of the network.
module_generator (function(pretrained, num_classes))
    Function that generates the network.
label (character(1))
```

The label of the network. #' @references Krizhevsky, Alex, Sutskever, Ilya, Hinton, E. G (2017). "Imagenet classification with deep convolutional neural networks." *Communications of the ACM*, **60**(6), 84–90. Sandler, Mark, Howard, Andrew, Zhu, Menglong, Zhmoginov, Andrey, Chen, Liang-Chieh (2018). "Mobilenetv2: Inverted residuals and linear bottlenecks." In *Proceedings of the IEEE conference on computer vision and pattern recognition*, 4510–4520. He, Kaiming, Zhang, Xiangyu, Ren, Shaoqing, Sun, Jian (2016). "Deep residual learning for image recognition." In *Proceedings of the IEEE conference on computer vision and pattern recognition*, 770–778. Simonyan, Karen, Zisserman, Andrew (2014). "Very deep convolutional networks for large-scale image recognition." *arXiv preprint arXiv:1409.1556*.

```
optimizer (TorchOptimizer)
```

The optimizer to use for training. Per default, *adam* is used.

```
loss (TorchLoss)
```

The loss used to train the network. Per default, *mse* is used for regression and *cross_entropy* for classification.

```
callbacks (list() of TorchCallbacks)
```

The callbacks. Must have unique ids.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

```
LearnerTorchVision$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

```
mlr_learners.torch_featureless
```

Featureless Torch Learner

Description

Featureless torch learner. Output is a constant weight that is learned during training. For classification, this should (asymptoptically) result in a majority class prediction when using the standard cross-entropy loss. For regression, this should result in the median for L1 loss and in the mean for L2 loss.

Dictionary

This Learner can be instantiated using the sugar function lrn():

```
lrn("classif.torch_featureless", ...)
lrn("regr.torch_featureless", ...)
```

Properties

- Supported task types: 'classif', 'regr'
- Predict Types:
 - classif: 'response', 'prob'
 - regr: 'response'
- Feature Types: "logical", "integer", "numeric", "character", "factor", "ordered", "POSIXct", "lazy_tensor"
- Required Packages: mlr3, mlr3torch, torch

Parameters

Only those from LearnerTorch.

Super classes

```
mlr3::Learner -> mlr3torch::LearnerTorch -> LearnerTorchFeatureless
```

Methods

Public methods:

- LearnerTorchFeatureless\$new()
- LearnerTorchFeatureless\$clone()

Method new(): Creates a new instance of this R6 class.

Usage:

```
LearnerTorchFeatureless$new(
    task_type,
   optimizer = NULL,
    loss = NULL,
   callbacks = list()
 )
 Arguments:
 task_type (character(1))
     The task type, either "classif" or "regr".
 optimizer (TorchOptimizer)
     The optimizer to use for training. Per default, adam is used.
 loss (TorchLoss)
     The loss used to train the network. Per default, mse is used for regression and cross_entropy
     for classification.
 callbacks (list() of TorchCallbacks)
     The callbacks. Must have unique ids.
Method clone(): The objects of this class are cloneable with this method.
 LearnerTorchFeatureless$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

See Also

 $Other\ Learner:\ mlr_learners.mlp,\ mlr_learners.tab_resnet,\ mlr_learners_torch,\ mlr_learners_torch_image,\ mlr_learners_torch_model$

Examples

```
# Define the Learner and set parameter values
learner = lrn("classif.torch_featureless")
learner$param_set$set_values(
   epochs = 1, batch_size = 16, device = "cpu"
)

# Define a Task
task = tsk("iris")

# Create train and test set
ids = partition(task)

# Train the learner on the training ids
learner$train(task, row_ids = ids$train)

# Make predictions for the test rows
predictions = learner$predict(task, row_ids = ids$test)
```

Score the predictions
predictions\$score()

mlr_learners_torch

Base Class for Torch Learners

Description

This base class provides the basic functionality for training and prediction of a neural network. All torch learners should inherit from this class.

Validation

To specify the validation data, you can set the \$validate field of the Learner, which can be set to:

- NULL: no validation
- ratio: only proportion 1 ratio of the task is used for training and ratio is used for validation.
- "test" means that the "test" task of a resampling is used and is not possible when calling \$train() manually.
- "predefined": This will use the predefined \$internal_valid_task of a mlr3::Task.

This validation data can also be used for early stopping, see the description of the Learner's parameters.

Saving a Learner

In order to save a LearnerTorch for later usage, it is necessary to call the \$marshal() method on the Learner before writing it to disk, as the object will otherwise not be saved correctly. After loading a marshaled LearnerTorch into R again, you then need to call \$unmarshal() to transform it into a useable state.

Early Stopping and Tuning

In order to prevent overfitting, the LearnerTorch class allows to use early stopping via the patience and min_delta parameters, see the Learner's parameters. When tuning a LearnerTorch it is also possible to combine the explicit tuning via mlr3tuning and the LearnerTorch's internal tuning of the epochs via early stopping. To do so, you just need to include epochs = to_tune(upper = <upper>, internal = TRUE) in the search space, where <upper> is the maximally allowed number of epochs, and configure the early stopping.

Model

The Model is a list of class "learner_torch_model" with the following elements:

- network :: The trained network.
- optimizer :: The \$state_dict() optimizer used to train the network.
- loss_fn :: The \$state_dict() of the loss used to train the network.
- callbacks :: The callbacks used to train the network.
- seed:: The seed that was / is used for training and prediction.
- epochs:: How many epochs the model was trained for (early stopping).
- task_col_info :: A data.table() containing information about the train-task.

Parameters

General:

The parameters of the optimizer, loss and callbacks, prefixed with "opt.", "loss." and "cb. <callback id>." respectively, as well as:

- epochs :: integer(1)
 The number of epochs.
- device :: character(1)
 The device. One of "auto", "cpu", or "cuda" or other values defined in mlr_reflections\$torch\$devices.
 The value is initialized to "auto", which will select "cuda" if possible, then try "mps" and otherwise fall back to "cpu".
- num_threads :: integer(1)

 The number of threads for intraop pararallelization (if device is "cpu"). This value is initialized to 1.
- seed :: integer(1) or "random" or NULL

 The torch seed that is used during training and prediction. This value is initialized to "random",
 which means that a random seed will be sampled at the beginning of the training phase. This
 seed (either set or randomly sampled) is available via \$model\$seed after training and used
 during prediction. Note that by setting the seed during the training phase this will mean that
 by default (i.e. when seed is "random"), clones of the learner will use a different seed. If set
 to NULL, no seeding will be done.

Evaluation:

- measures_train :: Measure or list() of Measures.
 Measures to be evaluated during training.
- measures_valid :: Measure or list() of Measures. Measures to be evaluated during validation.
- eval_freq :: integer(1)

 How often the train / validation predictions are evaluated using measures_train / measures_valid.

 This is initialized to 1. Note that the final model is always evaluated.

Early Stopping:

• patience :: integer(1)

This activates early stopping using the validation scores. If the performance of a model does not improve for patience evaluation steps, training is ended. Note that the final model is stored in the learner, not the best model. This is initialized to 0, which means no early stopping. The first entry from measures_valid is used as the metric. This also requires to specify the \$validate field of the Learner, as well as measures_valid.

• min_delta :: double(1)
The minimum improvement threshold (>) for early stopping. Is initialized to 0.

Dataloader:

- batch_size :: integer(1) The batch size (required).
- shuffle :: logical(1)
 Whether to shuffle the instances in the dataset. Default is FALSE. This does not impact validation.
- sampler :: torch::sampler
 Object that defines how the dataloader draw samples.
- batch_sampler :: torch::sampler
 Object that defines how the dataloader draws batches.
- num_workers :: integer(1)

 The number of workers for data loading (batches are loaded in parallel). The default is 0, which means that data will be loaded in the main process.
- collate_fn :: function How to merge a list of samples to form a batch.
- pin_memory :: logical(1)
 Whether the dataloader copies tensors into CUDA pinned memory before returning them.
- drop_last :: logical(1)
 Whether to drop the last training batch in each epoch during training. Default is FALSE.
- timeout :: numeric(1)
 The timeout value for collecting a batch from workers. Negative values mean no timeout and the default is -1.
- worker_init_fn:: function(id)
 A function that receives the worker id (in [1, num_workers]) and is exectued after seeding on the worker but before data loading.
- worker_globals :: list() | character()
 When loading data in parallel, this allows to export globals to the workers. If this is a character vector, the objects in the global environment with those names are copied to the workers.
- worker_packages :: character()
 Which packages to load on the workers.

Also see torch::dataloder for more information.

Inheriting

There are no seperate classes for classification and regression to inherit from. Instead, the task_type must be specified as a construction argument. Currently, only classification and regression are supported.

When inheriting from this class, one should overload two private methods:

.network(task, param_vals)(Task, list()) -> nn_module

Construct a torch::nn_module object for the given task and parameter values, i.e. the neural network that is trained by the learner. For classification, the output of this network are expected to be the scores before the application of the final softmax layer.

.dataset(task, param_vals)(Task, list()) -> torch::dataset

Create the dataset for the task. Must respect the parameter value of the device. Moreover, one needs to pay attention respect the row ids of the provided task.

It is also possible to overwrite the private .dataloader() method instead of the .dataset() method. Per default, a dataloader is constructed using the output from the .dataset() method. However, this should respect the dataloader parameters from the ParamSet.

• .dataloader(task, param_vals)
(Task, list()) -> torch::dataloader
Create a dataloader from the task. Needs to respect at least batch_size and shuffle (otherwise predictions can be permuted).

To change the predict types, the private .encode_prediction() method can be overwritten:

.encode_prediction(predict_tensor, task, param_vals)
 (torch_tensor, Task, list()) -> list()
 Take in the raw predictions from self\$network (predict_tensor) and encode them into a format that can be converted to valid mlr3 predictions using mlr3::as_prediction_data().
 This method must take self\$predict_type into account.

While it is possible to add parameters by specifying the param_set construction argument, it is currently not possible to remove existing parameters, i.e. those listed in section *Parameters*. None of the parameters provided in param_set can have an id that starts with "loss.", "opt.", or "cb.", as these are preserved for the dynamically constructed parameters of the optimizer, the loss function, and the callbacks.

To perform additional input checks on the task, the private .verify_train_task(task, param_vals) and .verify_predict_task(task, param_vals) can be overwritten.

For learners that have other construction arguments that should change the hash of a learner, it is required to implement the private \$.additional_phash_input().

Super class

mlr3::Learner -> LearnerTorch

Active bindings

```
validate How to construct the internal validation data. This parameter can be either NULL, a ratio
     in (0, 1), "test", or "predefined".
loss (TorchLoss)
     The torch loss.
optimizer (TorchOptimizer)
     The torch optimizer.
callbacks (list() of TorchCallbacks)
     List of torch callbacks. The ids will be set as the names.
internal_valid_scores Retrieves the internal validation scores as a named list(). Specify the
     $validate field and the measures_valid parameter to configure this. Returns NULL if learner
     is not trained yet.
internal_tuned_values When early stopping is activate, this returns a named list with the early-
     stopped epochs, otherwise an empty list is returned. Returns NULL if learner is not trained
     yet.
marshaled (logical(1))
     Whether the learner is marshaled.
network (nn_module())
     Shortcut for learner$model$network.
param_set (ParamSet)
     The parameter set
hash (character(1))
     Hash (unique identifier) for this object.
phash (character(1))
     Hash (unique identifier) for this partial object, excluding some components which are varied
     systematically during tuning (parameter values).
```

Methods

Public methods:

- LearnerTorch\$new()
- LearnerTorch\$format()
- LearnerTorch\$print()
- LearnerTorch\$marshal()
- LearnerTorch\$unmarshal()
- LearnerTorch\$dataset()
- LearnerTorch\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
LearnerTorch$new(
  id,
  task_type,
  param_set,
```

```
properties,
   man,
    label,
    feature_types,
    optimizer = NULL,
    loss = NULL,
    packages = character(),
    predict_types = NULL,
    callbacks = list()
 )
 Arguments:
 id (character(1))
     The id for of the new object.
 task_type (character(1))
     The task type.
 param_set (ParamSet or alist())
     Either a parameter set, or an alist() containing different values of self, e.g. alist(private$.param_set1,
     private$.param_set2), from which a ParamSet collection should be created.
 properties (character())
     The properties of the object. See mlr_reflections$learner_properties for available
     values.
 man (character(1))
     String in the format [pkg]::[topic] pointing to a manual page for this object. The refer-
     enced help package can be opened via method $help().
 label (character(1))
     Label for the new instance.
 feature_types (character())
     The feature types. See mlr_reflections$task_feature_types for available values, Ad-
     ditionally, "lazy_tensor" is supported.
 optimizer (NULL or TorchOptimizer)
     The optimizer to use for training. Defaults to adam.
 loss (NULL or TorchLoss)
     The loss to use for training. Defaults to MSE for regression and cross entropy for classifi-
     cation.
 packages (character())
     The R packages this object depends on.
 predict_types (character())
     The predict types. See mlr_reflections$learner_predict_types for available values.
     For regression, the default is "response". For classification, this defaults to "response"
     and "prob". To deviate from the defaults, it is necessary to overwrite the private $.encode_prediction()
     method, see section Inheriting.
 callbacks (list() of TorchCallbacks)
     The callbacks to use for training. Defaults to an empty list(), i.e. no callbacks.
Method format(): Helper for print outputs.
 Usage:
```

```
LearnerTorch$format(...)
 Arguments:
 ... (ignored).
Method print(): Prints the object.
 Usage:
 LearnerTorch$print(...)
 Arguments:
 ... (any)
     Currently unused.
Method marshal(): Marshal the learner.
 Usage:
 LearnerTorch$marshal(...)
 Arguments:
 ... (any)
     Additional parameters.
 Returns: self
Method unmarshal(): Unmarshal the learner.
 Usage:
 LearnerTorch$unmarshal(...)
 Arguments:
 ... (any)
     Additional parameters.
 Returns: self
Method dataset(): Create the dataset for a task.
 Usage:
 LearnerTorch$dataset(task)
 Arguments:
 task Task
     The task
 Returns: dataset
Method clone(): The objects of this class are cloneable with this method.
 LearnerTorch$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

See Also

Other Learner: mlr_learners.mlp, mlr_learners.tab_resnet, mlr_learners.torch_featureless, mlr_learners_torch_image, mlr_learners_torch_model

```
mlr_learners_torch_image

Image Learner
```

Description

Base Class for Image Learners. The features are assumed to be a single lazy_tensor column in RGB format.

Parameters

Parameters include those inherited from LearnerTorch and the param_set construction argument.

Super classes

```
mlr3::Learner -> mlr3torch::LearnerTorch -> LearnerTorchImage
```

Methods

Public methods:

- LearnerTorchImage\$new()
- LearnerTorchImage\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
LearnerTorchImage$new(
  id,
  task_type,
  param_set = ps(),
  label,
  optimizer = NULL,
  loss = NULL,
  callbacks = list(),
  packages = c("torchvision", "magick"),
  man,
  properties = NULL,
  predict_types = NULL
Arguments:
id (character(1))
   The id for of the new object.
task_type (character(1))
   The task type.
param_set (ParamSet)
   The parameter set.
```

```
label (character(1))
     Label for the new instance.
 optimizer (TorchOptimizer)
     The torch optimizer.
 loss (TorchLoss)
     The loss to use for training.
 callbacks (list() of TorchCallbacks)
     The callbacks used during training. Must have unique ids. They are executed in the order
     in which they are provided
 packages (character())
     The R packages this object depends on.
 man (character(1))
     String in the format [pkg]::[topic] pointing to a manual page for this object. The refer-
     enced help package can be opened via method $help().
 properties (character())
     The properties of the object. See mlr_reflections$learner_properties for available
     values.
 predict_types (character())
     The predict types. See mlr_reflections$learner_predict_types for available values.
Method clone(): The objects of this class are cloneable with this method.
 Usage:
 LearnerTorchImage$clone(deep = FALSE)
 Arguments:
 deep Whether to make a deep clone.
```

See Also

Other Learner: mlr_learners.mlp, mlr_learners.tab_resnet, mlr_learners.torch_featureless, mlr_learners_torch, mlr_learners_torch_model

```
mlr_learners_torch_model
```

Learner Torch Model

Description

Create a torch learner from an instantiated nn_module(). For classification, the output of the network must be the scores (before the softmax).

Parameters

See LearnerTorch

Super classes

```
mlr3::Learner -> mlr3torch::LearnerTorch -> LearnerTorchModel
```

Active bindings

```
network_stored (nn_module or NULL)
The network that will be trained. After calling $train(), this is NULL.
ingress_tokens (named list() with TorchIngressToken or NULL)
The ingress tokens. Must be non-NULL when calling $train().
```

Methods

Public methods:

- LearnerTorchModel\$new()
- LearnerTorchModel\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
LearnerTorchModel$new(
  network = NULL,
  ingress_tokens = NULL,
  task_type,
  properties = NULL,
  optimizer = NULL,
  loss = NULL,
  callbacks = list(),
  packages = character(0),
  feature_types = NULL
Arguments:
network (nn_module)
    An instantiated nn_module. Is not cloned during construction. For classification, outputs
    must be the scores (before the softmax).
ingress_tokens (list of TorchIngressToken())
    A list with ingress tokens that defines how the dataloader will be defined.
task_type (character(1))
    The task type.
properties (NULL or character())
    The properties of the learner. Defaults to all available properties for the given task type.
optimizer (TorchOptimizer)
    The torch optimizer.
loss (TorchLoss)
    The loss to use for training.
callbacks (list() of TorchCallbacks)
    The callbacks used during training. Must have unique ids. They are executed in the order
```

The callbacks used during training. Must have unique ids. They are executed in the order in which they are provided

```
packages (character())
    The R packages this object depends on.
feature_types (NULL or character())
    The feature types. Defaults to all available feature types.

Method clone(): The objects of this class are cloneable with this method.
    Usage:
    LearnerTorchModel$clone(deep = FALSE)
    Arguments:
    deep Whether to make a deep clone.
```

See Also

```
Other Learners mlr_learners.mlp, mlr_learners.tab_resnet, mlr_learners.torch_featureless, mlr_learners_torch, mlr_learners_torch_image

Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()
```

Examples

```
# We show the learner using a classification task
# The iris task has 4 features and 3 classes
network = nn_linear(4, 3)
task = tsk("iris")
# This defines the dataloader.
# It loads all 4 features, which are also numeric.
# The shape is (NA, 4) because the batch dimension is generally NA
ingress_tokens = list(
 input = TorchIngressToken(task$feature_names, batchgetter_num, c(NA, 4))
# Creating the learner and setting required parameters
learner = lrn("classif.torch_model",
 network = network,
 ingress_tokens = ingress_tokens,
 batch_size = 16,
 epochs = 1,
 device = "cpu"
)
# A simple train-predict
ids = partition(task)
learner$train(task, ids$train)
learner$predict(task, ids$test)
```

Description

Calls torchvision::transform_center_crop, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
size	untyped	-	
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

```
\label{linear_pipeops_augment_color_jitter} Pipe OpPreproc Torch Augment Color Jitter
```

Description

Calls torchvision::transform_color_jitter, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
brightness	numeric	0		$[0,\infty)$
contrast	numeric	0		$[0,\infty)$
saturation	numeric	0		$[0,\infty)$
hue	numeric	0		$[0,\infty)$
stages	character	-	train, predict, both	-

affect_columns untyped selector_all()

```
mlr_pipeops_augment_crop
```

PipeOpPreprocTorchAugmentCrop

Description

Calls torchvision::transform_crop, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

∀1	\mathcal{C}
top integer - (-	$-\infty, \infty)$
left integer - (-	$-\infty, \infty)$
height integer - (-	$-\infty, \infty)$
width integer - (-	$-\infty, \infty)$
stages character - train, predict, both -	
affect_columns untyped selector_all() -	

```
mlr_pipeops_augment_hflip
```

PipeOpPreprocTorchAugmentHflip

Description

Calls torchvision::transform_hflip, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

 $\label{line:continuous} {\it PipeOpPreprocTorchAugmentRandomAffine} \\ {\it PipeOpPreprocTorchAugmentRandomAffine}$

Description

Calls torchvision::transform_random_affine, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
degrees	untyped	-		-
translate	untyped	NULL		-
scale	untyped	NULL		-
resample	integer	0		$(-\infty, \infty)$
fillcolor	untyped	0		-
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()	-	-

```
mlr_pipeops_augment_random_choice
```

Pipe Op Preproc Torch Augment Random Choice

Description

Calls torchvision::transform_random_choice, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
transforms	untyped	-	
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

```
mlr_pipeops_augment_random_crop
```

 ${\it Pipe Op Preproc Torch Augment Random Crop}$

Description

Calls torchvision::transform_random_crop, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
size	untyped	-	
padding	untyped	NULL	
pad_if_needed	logical	FALSE	TRUE, FALSE
fill	untyped	0L	
padding_mode	character	constant	constant, edge, reflect, symmetric

```
stages character - train, predict, both affect_columns untyped selector_all()
```

```
\label{lip} \verb| mlr_pipeops_augment_random_horizontal_flip| \\ PipeOpPreprocTorchAugmentRandomHorizontalFlip| \\
```

Description

Calls torchvision::transform_random_horizontal_flip, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
p	numeric	0.5		[0, 1]
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

Description

Calls torchvision::transform_random_order, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
transforms	untyped	-	
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

Description

Calls torchvision::transform_random_resized_crop, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
size	untyped	-		-
scale	untyped	c(0.08, 1)		-
ratio	untyped	c(3/4, 4/3)		-
interpolation	integer	2		[0, 3]
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
\label{lip} \verb| mlr_pipe ops_augment_random_vertical_flip| \\ Pipe OpP reproc Torch Augment Random Vertical Flip| \\
```

Description

Calls torchvision::transform_random_vertical_flip, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
p	numeric	0.5		[0, 1]
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
mlr_pipeops_augment_resized_crop

PipeOpPreprocTorchAugmentResizedCrop
```

Description

Calls torchvision::transform_resized_crop, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

 ${\tt R6Class\ inheriting\ from\ PipeOpTaskPreprocTorch.}$

Parameters

Id	Type	Default	Levels	Range
top	integer	-		$(-\infty,\infty)$
left	integer	-		$(-\infty,\infty)$
height	integer	-		$(-\infty,\infty)$
width	integer	-		$(-\infty,\infty)$
size	untyped	-		-

```
{\tt mlr\_pipeops\_augment\_rotate}
```

PipeOpPreprocTorchAugmentRotate

Description

Calls torchvision::transform_rotate, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
angle	untyped	-		-
resample	integer	0		$(-\infty, \infty)$
expand	logical	FALSE	TRUE, FALSE	-
center	untyped	NULL		-
fill	untyped	NULL		-
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
mlr_pipeops_augment_vflip
```

PipeOpPreprocTorchAugmentVflip

Description

Calls torchvision::transform_vflip, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

62 mlr_pipeops_module

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

```
IdTypeDefaultLevelsstagescharacter-train, predict, bothaffect_columnsuntypedselector_all()
```

mlr_pipeops_module

Class for Torch Module Wrappers

Description

PipeOpModule wraps an nn_module or function that is being called during the train phase of this mlr3pipelines::PipeOp. By doing so, this allows to assemble PipeOpModules in a computational mlr3pipelines::Graph that represents either a neural network or a preprocessing graph of a lazy_tensor. In most cases it is easier to create such a network by creating a graph that generates this graph.

In most cases it is easier to create such a network by creating a structurally related graph consisting of nodes of class PipeOpTorchIngress and PipeOpTorch. This graph will then generate the graph consisting of PipeOpModules as part of the ModelDescriptor.

Input and Output Channels

The number and names of the input and output channels can be set during construction. They input and output "torch_tensor" during training, and NULL during prediction as the prediction phase currently serves no meaningful purpose.

State

The state is the value calculated by the public method shapes_out().

Parameters

No parameters.

Internals

During training, the wrapped nn_module / function is called with the provided inputs in the order in which the channels are defined. Arguments are **not** matched by name.

mlr_pipeops_module 63

Super class

```
mlr3pipelines::PipeOp -> PipeOpModule
```

Public fields

```
module (nn_module)
```

The torch module that is called during the training phase.

Methods

Public methods:

- PipeOpModule\$new()
- PipeOpModule\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpModule$new(
  id = "module",
  module = nn_identity(),
  inname = "input",
  outname = "output";
  param_vals = list(),
  packages = character(0)
)
Arguments:
id (character(1))
   The id for of the new object.
module (nn_module or function())
   The torch module or function that is being wrapped.
inname (character())
   The names of the input channels.
outname (character())
   The names of the output channels. If this parameter has length 1, the parameter module
   must return a tensor. Otherwise it must return a list() of tensors of corresponding length.
param_vals (named list())
   Parameter values to be set after construction.
packages (character())
   The R packages this object depends on.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpModule$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()

Other PipeOp: mlr_pipeops_torch_callbacks, mlr_pipeops_torch_optimizer
```

Examples

```
## creating an PipeOpModule manually
# one input and output channel
po_module = po("module",
  id = "linear",
  module = torch::nn_linear(10, 20),
  inname = "input",
  outname = "output"
x = torch::torch_randn(16, 10)
# This calls the forward function of the wrapped module.
y = po_module$train(list(input = x))
str(y)
# multiple input and output channels
nn_custom = torch::nn_module("nn_custom",
  initialize = function(in_features, out_features) {
   self$lin1 = torch::nn_linear(in_features, out_features)
   self$lin2 = torch::nn_linear(in_features, out_features)
  forward = function(x, z) {
    list(out1 = self$lin1(x), out2 = torch::nnf_relu(self$lin2(z)))
module = nn_custom(3, 2)
po_module = po("module",
  id = "custom",
  module = module,
  inname = c("x", "z"),
  outname = c("out1", "out2")
)
x = torch::torch_randn(1, 3)
z = torch::torch_randn(1, 3)
out = po_module train(list(x = x, z = z))
str(out)
# How such a PipeOpModule is usually generated
graph = po("torch_ingress_num") %>>% po("nn_linear", out_features = 10L)
result = graph$train(tsk("iris"))
# The PipeOpTorchLinear generates a PipeOpModule and adds it to a new (module) graph
result[[1]]$graph
```

```
linear_module = result[[1L]]$graph$pipeops$nn_linear
linear_module
formalArgs(linear_module$module)
linear_module$input$name

# Constructing a PipeOpModule using a simple function
po_add1 = po("module",
    id = "add_one",
    module = function(x) x + 1
)
input = list(torch_tensor(1))
po_add1$train(input)$output
```

```
mlr_pipeops_nn_avg_pool1d

1D Average Pooling
```

Description

Applies a 1D adaptive average pooling over an input signal composed of several input planes.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

- kernel_size :: (integer())
 The size of the window. Can be a single number or a vector.
- stride :: integer()
 The stride of the window. Can be a single number or a vector. Default: kernel_size.
- padding:: integer()
 Implicit zero paddings on both sides of the input. Can be a single number or a vector. Default:
- ceil_mode :: integer()
 When TRUE, will use ceil instead of floor to compute the output shape. Default: FALSE.
- count_include_pad :: logical(1)
 When TRUE, will include the zero-padding in the averaging calculation. Default: TRUE.

divisor_override :: logical(1)
 If specified, it will be used as divisor, otherwise size of the pooling region will be used. Default: NULL. Only available for dimension greater than 1.

Internals

```
Calls nn_avg_pool1d() during training.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchAvgPool -
> PipeOpTorchAvgPool1D
```

Methods

Public methods:

- PipeOpTorchAvgPool1D\$new()
- PipeOpTorchAvgPool1D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchAvgPool1D$new(id = "nn_avg_pool1d", param_vals = list())
Arguments:
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchAvgPool1D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu,
```

```
mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingresmlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_avg_pool1d")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_avg_pool2d

2D Average Pooling
```

Description

Applies a 2D adaptive average pooling over an input signal composed of several input planes.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

```
Calls nn_avg_pool2d() during training.
```

Parameters

- kernel_size :: (integer())
 The size of the window. Can be a single number or a vector.
- stride :: integer()
 The stride of the window. Can be a single number or a vector. Default: kernel_size.

- padding:: integer()
 Implicit zero paddings on both sides of the input. Can be a single number or a vector. Default:
 0.
- ceil_mode :: integer()
 When TRUE, will use ceil instead of floor to compute the output shape. Default: FALSE.
- count_include_pad :: logical(1)
 When TRUE, will include the zero-padding in the averaging calculation. Default: TRUE.
- divisor_override :: logical(1)
 If specified, it will be used as divisor, otherwise size of the pooling region will be used. Default: NULL. Only available for dimension greater than 1.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchAvgPool -
> PipeOpTorchAvgPool2D
```

Methods

Public methods:

- PipeOpTorchAvgPool2D\$new()
- PipeOpTorchAvgPool2D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchAvgPool2D$new(id = "nn_avg_pool2d", param_vals = list())
```

Arguments:

```
id (character(1))
```

Identifier of the resulting object.

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchAvgPool2D\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other\ PipeOps: \ mlr\_pipeops\_nn\_avg\_pool1d, \ mlr\_pipeops\_nn\_avg\_pool3d, \ mlr\_pipeops\_nn\_batch\_norm1d, \ mlr\_pipeops\_nn\_batch\_norm2d, \ mlr\_pipeops\_nn\_batch\_norm3d, \ mlr\_pipeops\_nn\_block, \ mlr\_pipeops\_nn\_celu, \ mlr\_pipeops\_nn\_conv1d, \ mlr\_pipeops\_nn\_conv2d, \ mlr\_pipeops\_nn\_conv_transpose1d, \ mlr\_pipeops\_nn\_conv\_transpose2d, \ mlr\_pipeops\_nn\_dropout, \ mlr\_pipeops\_nn\_elu, \ mlr\_pipeops\_nn\_elu, \ mlr\_pipeops\_nn\_flatten, \ mlr\_pipeops\_nn\_gelu, \ mlr\_pipeops\_nn\_glu, \ mlr\_pipeops\_nn\_hardshrink, \ mlr\_pipeops\_nn\_hardsigmoid, \ mlr\_pipeops\_nn\_hardtanh, \ mlr\_pipeops\_nn\_hards, \ mlr\_pipeops\_nn\_hardshrink, \ mlr\_pip
```

```
mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingresmlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_avg_pool2d")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_avg_pool3d

3D Average Pooling
```

Description

Applies a 3D adaptive average pooling over an input signal composed of several input planes.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

```
Calls nn_avg_pool3d() during training.
```

Parameters

- kernel_size :: (integer())
 The size of the window. Can be a single number or a vector.
- stride :: integer()
 The stride of the window. Can be a single number or a vector. Default: kernel_size.
- padding :: integer()
 Implicit zero paddings on both sides of the input. Can be a single number or a vector. Default:
 0.
- ceil_mode :: integer()
 When TRUE, will use ceil instead of floor to compute the output shape. Default: FALSE.
- count_include_pad :: logical(1)
 When TRUE, will include the zero-padding in the averaging calculation. Default: TRUE.
- divisor_override :: logical(1)
 If specified, it will be used as divisor, otherwise size of the pooling region will be used. Default: NULL. Only available for dimension greater than 1.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchAvgPool -
> PipeOpTorchAvgPool3D
```

Methods

Public methods:

- PipeOpTorchAvgPool3D\$new()
- PipeOpTorchAvgPool3D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchAvgPool3D$new(id = "nn_avg_pool3d", param_vals = list())
```

Arguments:

```
id (character(1))
```

Identifier of the resulting object.

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage.

```
PipeOpTorchAvgPool3D$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoi mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingre mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_avg_pool3d")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_batch_norm1d

1D Batch Normalization

Description

Applies Batch Normalization for each channel across a batch of data.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

- eps::numeric(1)
 - A value added to the denominator for numerical stability. Default: 1e-5.
- momentum :: numeric(1)
 - The value used for the running_mean and running_var computation. Can be set to NULL for cumulative moving average (i.e. simple average). Default: 0.1
- affine :: logical(1) a boolean value that when set to TRUE, this module has learnable affine parameters. Default: TRUE
- track_running_stats :: logical(1) a boolean value that when set to TRUE, this module tracks the running mean and variance, and when set to FALSE, this module does not track such statistics and always uses batch statistics in both training and eval modes. Default: TRUE

Internals

Calls torch::nn_batch_norm1d(). The parameter num_features is inferred as the second dimension of the input shape.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchBatchNorm
-> PipeOpTorchBatchNorm1D
```

Methods

Public methods:

- PipeOpTorchBatchNorm1D\$new()
- PipeOpTorchBatchNorm1D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchBatchNorm1D$new(id = "nn_batch_norm1d", param_vals = list())
```

Arguments:

```
id (character(1))
```

Identifier of the resulting object.

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

```
PipeOpTorchBatchNorm1D$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoi mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingre mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_batch_norm1d")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_batch_norm2d

2D Batch Normalization

Description

Applies Batch Normalization for each channel across a batch of data.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

Calls torch::nn_batch_norm2d(). The parameter num_features is inferred as the second dimension of the input shape.

Parameters

- eps::numeric(1)
 A value added to the denominator for numerical stability. Default: 1e-5.
- momentum:: numeric(1)

 The value used for the running_mean and running_var computation. Can be set to NULL for cumulative moving average (i.e. simple average). Default: 0.1
- affine :: logical(1) a boolean value that when set to TRUE, this module has learnable affine parameters. Default: TRUE
- track_running_stats :: logical(1) a boolean value that when set to TRUE, this module tracks the running mean and variance, and when set to FALSE, this module does not track such statistics and always uses batch statistics in both training and eval modes. Default: TRUE

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchBatchNorm
-> PipeOpTorchBatchNorm2D
```

Methods

Public methods:

- PipeOpTorchBatchNorm2D\$new()
- PipeOpTorchBatchNorm2D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchBatchNorm2D$new(id = "nn_batch_norm2d", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchBatchNorm2D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoi mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingre mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_batch_norm2d")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_batch_norm3d

3D Batch Normalization
```

Description

Applies Batch Normalization for each channel across a batch of data.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

Calls torch::nn_batch_norm3d(). The parameter num_features is inferred as the second dimension of the input shape.

Parameters

- eps::numeric(1)
 A value added to the denominator for numerical stability. Default: 1e-5.
- momentum:: numeric(1)

 The value used for the running_mean and running_var computation. Can be set to NULL for cumulative moving average (i.e. simple average). Default: 0.1
- affine :: logical(1) a boolean value that when set to TRUE, this module has learnable affine parameters. Default: TRUE
- track_running_stats :: logical(1) a boolean value that when set to TRUE, this module tracks the running mean and variance, and when set to FALSE, this module does not track such statistics and always uses batch statistics in both training and eval modes. Default: TRUE

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchBatchNorm
-> PipeOpTorchBatchNorm3D
```

Methods

Public methods:

- PipeOpTorchBatchNorm3D\$new()
- PipeOpTorchBatchNorm3D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchBatchNorm3D$new(id = "nn_batch_norm3d", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchBatchNorm3D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, $\verb|mlr_pipeops_nn_elu|, \verb|mlr_pipeops_nn_flatten|, \verb|mlr_pipeops_nn_gelu|, \|mlr_pipeops_nn_gelu|, \|$ mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoi mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingre mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_batch_norm3d")
pipeop
# The available parameters
pipeop$param_set
```

Description

Repeat a block n_blocks times.

Parameters

The parameters available for the block itself, as well as

n_blocks :: integer(1)
 How often to repeat the block.

Input and Output Channels

The PipeOp sets its input and output channels to those from the block (Graph) it received during construction.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Super classes

```
\verb|mlr3pipelines::PipeOp-> \verb|mlr3torch::PipeOpTorch-> PipeOpTorchBlock||
```

Active bindings

```
block (Graph)
```

The neural network segment that is repeated by this PipeOp.

Methods

Public methods:

- PipeOpTorchBlock\$new()
- PipeOpTorchBlock\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
```

```
PipeOpTorchBlock$new(block, id = "nn_block", param_vals = list())
```

Arguments:

block (Graph)

A graph consisting primarily of PipeOpTorch objects that is to be repeated.

id (character(1))

The id for of the new object.

param_vals (named list())

Parameter values to be set after construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchBlock\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge_nlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
```

mlr_pipeops_nn_celu 79

```
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
block = po("nn_linear") %>>% po("nn_relu")
po_block = po("nn_block", block,
nn_linear.out_features = 10L, n_blocks = 3)
network = po("torch_ingress_num") %>>%
po_block %>>%
po("nn_head") %>>%
po("torch_loss", t_loss("cross_entropy")) %>>%
po("torch_optimizer", t_opt("adam")) %>>%
po("torch_model_classif",
   batch_size = 50,
   epochs = 3)

task = tsk("iris")
network$train(task)
```

mlr_pipeops_nn_celu

CELU Activation Function

Description

```
Applies element-wise, CELU(x) = max(0, x) + min(0, \alpha * (exp(x\alpha) - 1)).
```

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
alpha:: numeric(1)
The alpha value for the ELU formulation. Default: 1.0
inplace:: logical(1)
Whether to do the operation in-place. Default: FALSE.
```

Internals

```
Calls torch::nn_celu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchCELU
```

Methods

Public methods:

- PipeOpTorchCELU\$new()
- PipeOpTorchCELU\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchCELU$new(id = "nn_celu", param_vals = list())
Arguments:
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchCELU$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_bardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
```

```
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_celu")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_conv1d 1D Convolution
```

Description

Applies a 1D convolution over an input signal composed of several input planes.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

- out_channels :: integer(1)

 Number of channels produced by the convolution.
- kernel_size :: integer() Size of the convolving kernel.
- stride :: integer()
 Stride of the convolution. The default is 1.

```
    padding :: integer()
    'dilation * (kernel_size - 1) - padding' zero-padding will be added to both sides of the input.
    Default: 0.
```

• groups :: integer()

Number of blocked connections from input channels to output channels. Default: 1

• bias :: logical(1)
If 'TRUE', adds a learnable bias to the output. Default: 'TRUE'.

• dilation :: integer()
Spacing between kernel elements. Default: 1.

• padding_mode :: character(1)

The padding mode. One of "zeros", "reflect", "replicate", or "circular". Default is "zeros".

Internals

Calls torch::nn_conv1d() when trained. The paramter in_channels is inferred from the second dimension of the input tensor.

Super classes

```
mlr3pipelines::PipeOp->mlr3torch::PipeOpTorch->mlr3torch::PipeOpTorchConv->PipeOpTorchConv1D
```

Methods

Public methods:

- PipeOpTorchConv1D\$new()
- PipeOpTorchConv1D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchConv1D$new(id = "nn_conv1d", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchConv1D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d,
mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d,
mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_conv1d", kernel_size = 10, out_channels = 1)
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_conv2d 2D Convolution
```

Description

Applies a 2D convolution over an input image composed of several input planes.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

Calls torch::nn_conv2d() when trained. The paramter in_channels is inferred from the second dimension of the input tensor.

Parameters

- out_channels :: integer(1)

 Number of channels produced by the convolution.
- kernel_size :: integer() Size of the convolving kernel.
- stride :: integer()
 Stride of the convolution. The default is 1.
- padding :: integer()
 'dilation * (kernel_size 1) padding' zero-padding will be added to both sides of the input.

 Default: 0.
- groups :: integer()

 Number of blocked connections from input channels to output channels. Default: 1
- bias :: logical(1)
 If 'TRUE', adds a learnable bias to the output. Default: 'TRUE'.
- dilation :: integer()
 Spacing between kernel elements. Default: 1.
- padding_mode :: character(1)

 The padding mode. One of "zeros", "reflect", "replicate", or "circular". Default is "zeros".

Super classes

```
mlr3pipelines::Pipe0p->mlr3torch::Pipe0pTorch->mlr3torch::Pipe0pTorchConv->Pipe0pTorchConv2D
```

Methods

Public methods:

- PipeOpTorchConv2D\$new()
- PipeOpTorchConv2D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchConv2D$new(id = "nn_conv2d", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchConv2D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv3d,
mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d,
mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_conv2d", kernel_size = 10, out_channels = 1)
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_conv3d 3D Convolution
```

Description

Applies a 3D convolution over an input image composed of several input planes.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

Calls torch::nn_conv3d() when trained. The paramter in_channels is inferred from the second dimension of the input tensor.

Parameters

- out_channels :: integer(1)
 Number of channels produced by the convolution.
- kernel_size :: integer() Size of the convolving kernel.
- stride :: integer()
 Stride of the convolution. The default is 1.
- padding :: integer()
 'dilation * (kernel_size 1) padding' zero-padding will be added to both sides of the input.

 Default: 0.
- groups :: integer()

 Number of blocked connections from input channels to output channels. Default: 1
- bias :: logical(1)
 If 'TRUE', adds a learnable bias to the output. Default: 'TRUE'.
- dilation :: integer()
 Spacing between kernel elements. Default: 1.
- padding_mode :: character(1)

 The padding mode. One of "zeros", "reflect", "replicate", or "circular". Default is "zeros".

Super classes

```
mlr3pipelines::PipeOp->mlr3torch::PipeOpTorch->mlr3torch::PipeOpTorchConv->PipeOpTorchConv3D
```

Methods

Public methods:

- PipeOpTorchConv3D\$new()
- PipeOpTorchConv3D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchConv3D$new(id = "nn_conv3d", param_vals = list())
```

```
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

We would be a set during construction.
```

```
Usage:
PipeOpTorchConv3D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d,
mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_conv3d", kernel_size = 10, out_channels = 1)
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_conv_transpose1d

Transpose 1D Convolution

Description

Transpose 1D Convolution

Transpose 1D Convolution

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

Parameters

- out_channels :: integer(1)
 Number of output channels produce by the convolution.
- kernel_size :: integer() Size of the convolving kernel.
- stride :: integer()
 Stride of the convolution. Default: 1.
- padding :: integer()'
 'dilation * (kernel_size 1) padding' zero-padding will be added to both sides of the input.

 Default: 0.
- output_padding ::integer()
 Additional size added to one side of the output shape. Default: 0.
- groups :: integer()

 Number of blocked connections from input channels to output channels. Default: 1
- bias :: logical(1)
 If 'True', adds a learnable bias to the output. Default: 'TRUE'.
- dilation :: integer()
 Spacing between kernel elements. Default: 1.
- padding_mode :: character(1)

 The padding mode. One of "zeros", "reflect", "replicate", or "circular". Default is "zeros".

Internals

Calls nn_conv_transpose1d. The parameter in_channels is inferred as the second dimension of the input tensor.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchConvTranspose
-> PipeOpTorchConvTranspose1D
```

Methods

Public methods:

- PipeOpTorchConvTranspose1D\$new()
- PipeOpTorchConvTranspose1D\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchConvTranspose1D$new(id = "nn_conv_transpose1d", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

wise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchConvTranspose1D\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d,
mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_conv_transpose1d", kernel_size = 3, out_channels = 2)
pipeop
# The available parameters
pipeop$param_set
```

```
{\tt mlr\_pipeops\_nn\_conv\_transpose2d}
```

Transpose 2D Convolution

Description

Applies a 2D transposed convolution operator over an input image composed of several input planes, sometimes also called "deconvolution".

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

Calls nn_conv_transpose2d. The parameter in_channels is inferred as the second dimension of the input tensor.

Parameters

- out_channels :: integer(1)

 Number of output channels produce by the convolution.
- kernel_size :: integer() Size of the convolving kernel.
- stride :: integer()
 Stride of the convolution. Default: 1.
- padding :: integer()'
 'dilation * (kernel_size 1) padding' zero-padding will be added to both sides of the input.
 Default: 0.

```
• output_padding ::integer()
Additional size added to one side of the output shape. Default: 0.
```

• groups :: integer()

Number of blocked connections from input channels to output channels. Default: 1

• bias :: logical(1)

If 'True', adds a learnable bias to the output. Default: 'TRUE'.

• dilation::integer()

Spacing between kernel elements. Default: 1.

padding_mode :: character(1)
 The padding mode. One of "zeros", "reflect", "replicate", or "circular". Default is "zeros".

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchConvTranspose
-> PipeOpTorchConvTranspose2D
```

Methods

Public methods:

- PipeOpTorchConvTranspose2D\$new()
- PipeOpTorchConvTranspose2D\$clone()

Method new(): Creates a new instance of this R6 class.

Usage:

PipeOpTorchConvTranspose2D\$new(id = "nn_conv_transpose2d", param_vals = list())

Arguments:

id (character(1))

Identifier of the resulting object.

param_vals (list())

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchConvTranspose2D\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
```

```
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_conv_transpose2d", kernel_size = 3, out_channels = 2)
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_conv_transpose3d

**Transpose 3D Convolution**
```

Description

Applies a 3D transposed convolution operator over an input image composed of several input planes, sometimes also called "deconvolution"

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

Calls nn_conv_transpose3d. The parameter in_channels is inferred as the second dimension of the input tensor.

Parameters

- out_channels :: integer(1)
 Number of output channels produce by the convolution.
- kernel_size :: integer() Size of the convolving kernel.
- stride :: integer()
 Stride of the convolution. Default: 1.
- padding :: integer()'
 'dilation * (kernel_size 1) padding' zero-padding will be added to both sides of the input.
 Default: 0.
- output_padding ::integer()
 Additional size added to one side of the output shape. Default: 0.
- groups :: integer()

 Number of blocked connections from input channels to output channels. Default: 1
- bias :: logical(1)
 If 'True', adds a learnable bias to the output. Default: 'TRUE'.
- dilation :: integer()
 Spacing between kernel elements. Default: 1.
- padding_mode :: character(1)

 The padding mode. One of "zeros", "reflect", "replicate", or "circular". Default is "zeros".

Super classes

```
mlr3pipelines::PipeOp->mlr3torch::PipeOpTorch->mlr3torch::PipeOpTorchConvTranspose
-> PipeOpTorchConvTranspose3D
```

Methods

Public methods:

• PipeOpTorchConvTranspose3D\$new()

wise be set during construction.

• PipeOpTorchConvTranspose3D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchConvTranspose3D$new(id = "nn_conv_transpose3d", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchConvTranspose3D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_conv_transpose3d", kernel_size = 3, out_channels = 2)
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_dropout
```

Dropout

Description

During training, randomly zeroes some of the elements of the input tensor with probability p using samples from a Bernoulli distribution.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• p:: numeric(1)
Probability of an element to be zeroed. Default: 0.5 inplace
```

```
• inplace :: logical(1)

If set to TRUE, will do this operation in-place. Default: FALSE.
```

Internals

```
Calls torch::nn_dropout() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchDropout
```

Methods

Public methods:

- PipeOpTorchDropout\$new()
- PipeOpTorchDropout\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchDropout$new(id = "nn_dropout", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
```

param_vals (list())
 List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchDropout$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

96 mlr_pipeops_nn_elu

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, $\verb|mlr_pipeops_nn_softmax|, \verb|mlr_pipeops_nn_softplus|, \verb|mlr_pipeops_nn_softshrink|, \verb|mlr_pipeops_nn_softsign|, \verb|mlr_pipeops_nn_softshrink|, \|mlr_pipeops_nn_softshrink|, \|mlr_pipeo$ mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_dropout")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_elu

ELU Activation Function

Description

Applies element-wise,

```
ELU(x) = max(0, x) + min(0, \alpha * (exp(x) - 1))
```

.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

mlr_pipeops_nn_elu 97

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• alpha :: numeric(1)
The alpha value for the ELU formulation. Default: 1.0
```

• inplace :: logical(1)
Whether to do the operation in-place. Default: FALSE.

Internals

```
Calls torch::nn_elu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchELU
```

Methods

Public methods:

- PipeOpTorchELU\$new()
- PipeOpTorchELU\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchELU$new(id = "nn_elu", param_vals = list())
Arguments:
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings overwriting the hyperparameter
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchELU$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_elu")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_flatten
```

Flattens a Tensor

Description

For use with nn_sequential.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
start_dim:: integer(1)
At wich dimension to start flattening. Default is 2. end_dim:: integer(1)
At wich dimension to stop flattening. Default is -1.
```

Internals

```
Calls torch::nn_flatten() when trained.
```

Super classes

```
mlr3pipelines::Pipe0p -> mlr3torch::Pipe0pTorch -> Pipe0pTorchFlatten
```

Methods

Public methods:

- PipeOpTorchFlatten\$new()
- PipeOpTorchFlatten\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchFlatten$new(id = "nn_flatten", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings.
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchFlatten$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge_nlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
```

```
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_flatten")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_gelu

GELU Activation Function

Description

Gelu

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

approximate :: character(1)
 Whether to use an approximation algorithm. Default is "none".

Internals

```
Calls torch::nn_gelu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchGELU
```

mlr_pipeops_nn_gelu 101

Methods

Public methods:

- PipeOpTorchGELU\$new()
- PipeOpTorchGELU\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchGELU$new(id = "nn_gelu", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchGELU$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_gelu")
pipeop
# The available parameters
pipeop$param_set
```

102 mlr_pipeops_nn_glu

```
mlr_pipeops_nn_glu
```

GLU Activation Function

Description

The gated linear unit. Computes:

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• dim:: integer(1)
Dimension on which to split the input. Default: -1
```

Internals

```
Calls torch::nn_glu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchGLU
```

Methods

Public methods:

- PipeOpTorchGLU\$new()
- PipeOpTorchGLU\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchGLU$new(id = "nn_glu", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
```

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchGLU\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_glu")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_hardshrink

Hard Shrink Activation Function

Description

Applies the hard shrinkage function element-wise

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

• lambd :: numeric(1)
The lambda value for the Hardshrink formulation formulation. Default 0.5.

Internals

```
Calls torch::nn_hardshrink() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchHardShrink
```

Methods

Public methods:

- PipeOpTorchHardShrink\$new()
- PipeOpTorchHardShrink\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchHardShrink$new(id = "nn_hardshrink", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
```

param_vals (list())

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchHardShrink$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_hardshrink")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_hardsigmoid

Hard Sigmoid Activation Function

Description

Applies the element-wise function $\operatorname{Hardsigmoid}(x) = \frac{ReLU6(x+3)}{6}$

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

```
Calls torch::nn_hardsigmoid() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchHardSigmoid
```

Methods

Public methods:

- PipeOpTorchHardSigmoid\$new()
- PipeOpTorchHardSigmoid\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchHardSigmoid$new(id = "nn_hardsigmoid", param_vals = list())
```

```
Arguments:
```

```
id (character(1))

Identifier of the resulting phia
```

Identifier of the resulting object. param_vals (list())

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchHardSigmoid\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
```

```
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_hardsigmoid")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_hardtanh
```

Hard Tanh Activation Function

Description

Applies the HardTanh function element-wise.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• min_val :: numeric(1)
Minimum value of the linear region range. Default: -1.
```

```
• max_val :: numeric(1)

Maximum value of the linear region range. Default: 1.
```

```
• inplace :: logical(1)
Can optionally do the operation in-place. Default: FALSE.
```

Internals

```
Calls torch::nn_hardtanh() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchHardTanh
```

Methods

Public methods:

- PipeOpTorchHardTanh\$new()
- PipeOpTorchHardTanh\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchHardTanh$new(id = "nn_hardtanh", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchHardTanh$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_hardtanh")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_head

109

mlr_pipeops_nn_head Output Head

Description

Output head for classification and regresssion.

NOTE Because the method \$shapes_out() does not have access to the task, it returns c(NA, NA). When this PipeOp is trained however, the model descriptor has the correct output shape.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

• bias :: logical(1)
Whether to use a bias. Default is TRUE.

Internals

Calls torch::nn_linear() with the input and output features inferred from the input shape / task.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchHead
```

Methods

Public methods:

- PipeOpTorchHead\$new()
- PipeOpTorchHead\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchHead$new(id = "nn_head", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
```

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

PipeOpTorchHead\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_head")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_layer_norm
```

Layer Normalization

Description

Applies Layer Normalization for last certain number of dimensions.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

Parameters

- dims :: integer(1)

 The number of dimensions over which will be normalized (starting from the last dimension).
- elementwise_affine :: logical(1)
 Whether to learn affine-linear parameters initialized to 1 for weights and to 0 for biases. The default is TRUE.
- eps :: numeric(1)

 A value added to the denominator for numerical stability.

Internals

Calls torch::nn_layer_norm() when trained. The parameter normalized_shape is inferred as the dimensions of the last dims dimensions of the input shape.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchLayerNorm
```

Methods

Public methods:

- PipeOpTorchLayerNorm\$new()
- PipeOpTorchLayerNorm\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchLayerNorm$new(id = "nn_layer_norm", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings overwriting the hyperparameter settings that we
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

```
Method clone(): The objects of this class are cloneable with this method.
```

```
Usage:
PipeOpTorchLayerNorm$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d,
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_layer_norm", dims = 1)
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_leaky_relu

Leaky ReLU Activation Function
```

Description

```
Applies element-wise, LeakyReLU(x) = max(0, x) + negative_slope * min(0, x)
```

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• negative_slope :: numeric(1)
Controls the angle of the negative slope. Default: 1e-2.
```

• inplace :: logical(1)
Can optionally do the operation in-place. Default: 'FALSE'.

Internals

```
Calls torch::nn_hardswish() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchLeakyReLU
```

Methods

Public methods:

- PipeOpTorchLeakyReLU\$new()
- PipeOpTorchLeakyReLU\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchLeakyReLU$new(id = "nn_leaky_relu", param_vals = list())
```

Arguments:

```
id (character(1))
```

Identifier of the resulting object.

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

```
PipeOpTorchLeakyReLU$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_leaky_relu")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_linear Linear Layer
```

Description

Applies a linear transformation to the incoming data: $y = xA^T + b$.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• out_features :: integer(1)
The output features of the linear layer.
```

• bias :: logical(1)

Whether to use a bias. Default is TRUE.

Internals

Calls torch::nn_linear() when trained where the parameter in_features is inferred as the second to last dimension of the input tensor.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchLinear
```

Methods

Public methods:

- PipeOpTorchLinear\$new()
- PipeOpTorchLinear\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchLinear$new(id = "nn_linear", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

```
PipeOpTorchLinear$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
```

```
mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_linear", out_features = 10)
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_log_sigmoid
```

Log Sigmoid Activation Function

Description

```
Applies element-wise LogSigmoid(x_i) = log(\frac{1}{1 + exp(-x_i)})
```

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

```
Calls torch::nn_log_sigmoid() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchLogSigmoid
```

Methods

Public methods:

- PipeOpTorchLogSigmoid\$new()
- PipeOpTorchLogSigmoid\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchLogSigmoid$new(id = "nn_log_sigmoid", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchLogSigmoid$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
\verb|mlr_pipeops_nn_linear|, \verb|mlr_pipeops_nn_max_pool1d|, \verb|mlr_pipeops_nn_max_pool2d|, \verb|mlr_pipeops_nn_max_pool3d|, \verb|mlr_pipeops_nn_max_pool3d|, \verb|mlr_pipeops_nn_max_pool2d|, \verb|mlr_pipeops_nn_max_pool3d|, \|mlr_pipeops_nn_max_pool3d|, \|mlr_pi
mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum,
mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape,
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_log_sigmoid")
pipeop
# The available parameters
pipeop$param_set
```

Description

Applies a 1D max pooling over an input signal composed of several input planes.

Input and Output Channels

If return_indices is FALSE during construction, there is one input channel 'input' and one output channel 'output'. If return_indices is TRUE, there are two output channels 'output' and 'indices'. For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

- kernel_size :: integer()
 The size of the window. Can be single number or a vector.
- stride :: (integer(1))

 The stride of the window. Can be a single number or a vector. Default: kernel_size
- padding :: integer()
 Implicit zero paddings on both sides of the input. Can be a single number or a tuple (padW,).
 Default: 0
- dilation :: integer()
 Controls the spacing between the kernel points; also known as the à trous algorithm. Default:
 1
- ceil_mode :: logical(1)
 When True, will use ceil instead of floor to compute the output shape. Default: FALSE

Internals

```
Calls torch::nn_max_pool1d() during training.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchMaxPool -
> PipeOpTorchMaxPool1D
```

Methods

Public methods:

- PipeOpTorchMaxPool1D\$new()
- PipeOpTorchMaxPool1D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMaxPool1D$new(
   id = "nn_max_pool1d",
   return_indices = FALSE,
   param_vals = list()
)
Arguments:
id (character(1))
   Identifier of the resulting object.
return_indices (logical(1))
   Whether to return the indices. If this is TRUE, there are two output channels "output" and "indices".
param_vals (list())
   List of bypermaneses the settings appropriation the bypermaneses that would other.
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchMaxPool1D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other\ PipeOps: \ mlr\_pipeops\_nn\_avg\_pool1d, \ mlr\_pipeops\_nn\_avg\_pool2d, \ mlr\_pipeops\_nn\_avg\_pool3d, \ mlr\_pipeops\_nn\_batch\_norm1d, \ mlr\_pipeops\_nn\_batch\_norm2d, \ mlr\_pipeops\_nn\_batch\_norm3d, \ mlr\_pipeops\_nn\_block, \ mlr\_pipeops\_nn\_celu, \ mlr\_pipeops\_nn\_conv1d, \ mlr\_pipeops\_nn\_conv2d, \ mlr\_pipeops\_nn\_conv3d, \ mlr\_pipeops\_nn\_conv\_transpose1d, \ mlr\_pipeops\_nn\_conv\_transpose2d, \ mlr\_pipeops\_nn\_conv\_transpose3d, \ mlr\_pipeops\_nn\_dropout, \ mlr\_pipeops\_nn\_elu, \ mlr\_pipeops\_nn\_plu, \ mlr\_pipeops\_nn\_hardshrink, \ mlr\_pipeops\_nn\_hardsigmoid, \ mlr\_pipeops\_nn\_hardtanh, \ mlr\_pipeops\_nn\_hard, \ mlr\_pipeops\_nn\_leaky\_relu, \ mlr\_pipeops\_nn\_leak
```

```
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool2d, mlr_pipeops_nn_max_pool3d mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_max_pool1d")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_max_pool2d

2D Max Pooling
```

Description

Applies a 2D max pooling over an input signal composed of several input planes.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

```
Calls torch::nn_max_pool2d() during training.
```

Input and Output Channels

If return_indices is FALSE during construction, there is one input channel 'input' and one output channel 'output'. If return_indices is TRUE, there are two output channels 'output' and 'indices'. For an explanation see PipeOpTorch.

Parameters

- kernel_size :: integer()
 The size of the window. Can be single number or a vector.
- stride :: (integer(1))

The stride of the window. Can be a single number or a vector. Default: kernel_size

- padding :: integer()
 Implicit zero paddings on both sides of the input. Can be a single number or a tuple (padW,).
 Default: 0
- dilation:: integer()
 Controls the spacing between the kernel points; also known as the à trous algorithm. Default:
- ceil_mode :: logical(1)
 When True, will use ceil instead of floor to compute the output shape. Default: FALSE

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchMaxPool -
> PipeOpTorchMaxPool2D
```

Methods

Public methods:

- PipeOpTorchMaxPool2D\$new()
- PipeOpTorchMaxPool2D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMaxPool2D$new(
   id = "nn_max_pool2d",
    return_indices = FALSE,
   param_vals = list()
)
Arguments:
id (character(1))
   Identifier of the resulting object.
return_indices (logical(1))
   Whether to return the indices. If this is TRUE, there are two output channels "output" and "indices".
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchMaxPool2D$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,mlr_pipeops_nn_log_sigmoid,mlr_pipeops_nn_max_pool1d,mlr_pipeops_nn_max_pool3d mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_max_pool2d")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_max_pool3d

3D Max Pooling
```

Description

Applies a 3D max pooling over an input signal composed of several input planes.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Internals

```
Calls torch::nn_max_pool3d() during training.
```

Input and Output Channels

If return_indices is FALSE during construction, there is one input channel 'input' and one output channel 'output'. If return_indices is TRUE, there are two output channels 'output' and 'indices'. For an explanation see PipeOpTorch.

Parameters

- kernel_size :: integer()
 The size of the window. Can be single number or a vector.
- stride :: (integer(1))
 The stride of the window. Can be a single number or a vector. Default: kernel_size
- padding :: integer()
 Implicit zero paddings on both sides of the input. Can be a single number or a tuple (padW,).
 Default: 0
- dilation :: integer()
 Controls the spacing between the kernel points; also known as the à trous algorithm. Default:

 1
- ceil_mode :: logical(1)
 When True, will use ceil instead of floor to compute the output shape. Default: FALSE

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchMaxPool -
> PipeOpTorchMaxPool3D
```

Methods

Public methods:

- PipeOpTorchMaxPool3D\$new()
- PipeOpTorchMaxPool3D\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMaxPool3D$new(
  id = "nn_max_pool3d",
  return_indices = FALSE,
  param_vals = list()
)
Arguments:
id (character(1))
  Identifier of the resulting object.
return_indices (logical(1))
  Whether to return the indices. If
```

Whether to return the indices. If this is TRUE, there are two output channels "output" and "indices".

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

PipeOpTorchMaxPool3D\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum,
mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape,
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_max_pool3d")
pipeop
# The available parameters
pipeop$param_set
```

Description

Base class for merge operations such as addition (PipeOpTorchMergeSum), multiplication (PipeOpTorchMergeProd or concatenation (PipeOpTorchMergeCat).

State

The state is the value calculated by the public method shapes_out().

Input and Output Channels

PipeOpTorchMerges has either a *vararg* input channel if the constructor argument innum is not set, or input channels "input1", ..., "input<innum>". There is one output channel "output". For an explanation see PipeOpTorch.

Parameters

See the respective child class.

Internals

Per default, the private\$.shapes_out() method outputs the broadcasted tensors. There are two things to be aware:

- 1. NAs are assumed to batch (this should almost always be the batch size in the first dimension).
- 2. Tensors are expected to have the same number of dimensions, i.e. missing dimensions are not filled with 1s. The reason is that again that the first dimension should be the batch dimension. This private method can be overwritten by PipeOpTorchs inheriting from this class.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchMerge
```

Methods

Public methods:

- PipeOpTorchMerge\$new()
- PipeOpTorchMerge\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMerge$new(
   id,
   module_generator,
   param_set = ps(),
   innum = 0,
   param_vals = list()
)
Arguments:
id (character(1))
   Identifier of the resulting object.
module_generator (nn_module_generator)
   The torch module generator.
```

```
param_set (ParamSet)
   The parameter set.
innum (integer(1))
   The number of inputs. Default is 0 which means there is one vararg input channel.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchMerge$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_su
mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape,
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

```
mlr_pipeops_nn_merge_cat

Merge by Concatenation
```

Description

Concatenates multiple tensors on a given dimension. No broadcasting rules are applied here, you must reshape the tensors before to have the same shape.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

PipeOpTorchMerges has either a *vararg* input channel if the constructor argument innum is not set, or input channels "input1", ..., "input<innum>". There is one output channel "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

• dim :: integer(1)

The dimension along which to concatenate the tensors.

Internals

Calls nn_merge_cat() when trained.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchMerge ->
PipeOpTorchMergeCat
```

Methods

Public methods:

- PipeOpTorchMergeCat\$new()
- PipeOpTorchMergeCat\$speak()
- PipeOpTorchMergeCat\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMergeCat$new(id = "nn_merge_cat", innum = 0, param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
innum (integer(1))
    The number of inputs. Default is 0 which means there is one vararg input channel.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

```
Method speak(): What does the cat say?
  Usage:
  PipeOpTorchMergeCat$speak()

Method clone(): The objects of this class are cloneable with this method.
  Usage:
  PipeOpTorchMergeCat$clone(deep = FALSE)
  Arguments:
  deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum,
mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape,
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_merge_cat")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_merge_prod

Merge by Product
```

Description

Calculates the product of all input tensors.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

PipeOpTorchMerges has either a *vararg* input channel if the constructor argument innum is not set, or input channels "input1", ..., "input<innum>". There is one output channel "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

Calls nn_merge_prod() when trained.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchMerge ->
PipeOpTorchMergeProd
```

Methods

Public methods:

- PipeOpTorchMergeProd\$new()
- PipeOpTorchMergeProd\$clone()

wise be set during construction.

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMergeProd$new(id = "nn_merge_prod", innum = 0, param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
innum (integer(1))
    The number of inputs. Default is 0 which means there is one vararg input channel.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchMergeProd$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_merge_prod")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_merge_sum
```

Merge by Summation

Description

Calculates the sum of all input tensors.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

PipeOpTorchMerges has either a *vararg* input channel if the constructor argument innum is not set, or input channels "input1", ..., "input<innum>". There is one output channel "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

Calls nn_merge_sum() when trained.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> mlr3torch::PipeOpTorchMerge ->
PipeOpTorchMergeSum
```

Methods

Public methods:

- PipeOpTorchMergeSum\$new()
- PipeOpTorchMergeSum\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchMergeSum$new(id = "nn_merge_sum", innum = 0, param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
innum (integer(1))
    The number of inputs. Default is 0 which means there is one vararg input channel.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchMergeSum$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

wise be set during construction.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode mlr_pipeops_torch_model_regr

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear,mlr_pipeops_nn_log_sigmoid,mlr_pipeops_nn_max_pool1d,mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_merge_sum")
pipeop
# The available parameters
pipeop$param_set
```

Description

Applies element-wise the function PReLU(x) = max(0, x) + weight * min(0, x) where weight is a learnable parameter.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

- num_parameters :: integer(1): Number of a to learn. Although it takes an int as input, there is only two values are legitimate: 1, or the number of channels at input. Default: 1.
- init :: numeric(1)
 T The initial value of a. Default: 0.25.

Internals

```
Calls torch::nn_prelu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchPReLU
```

Methods

Public methods:

- PipeOpTorchPReLU\$new()
- PipeOpTorchPReLU\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchPReLU$new(id = "nn_prelu", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchPReLU$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape,
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_prelu")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_relu

ReLU Activation Function

Description

Applies the rectified linear unit function element-wise.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

mlr_pipeops_nn_relu 135

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• inplace :: logical(1)
Whether to do the operation in-place. Default: FALSE.
```

Internals

```
Calls torch::nn_relu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchReLU
```

Methods

Public methods:

- PipeOpTorchReLU\$new()
- PipeOpTorchReLU\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchReLU$new(id = "nn_relu", param_vals = list())

Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchReLU$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

wise be set during construction.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_relu")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_relu6 ReLU6 Activation Function

Description

Applies the element-wise function ReLU6(x) = min(max(0, x), 6).

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

• inplace :: logical(1)
Whether to do the operation in-place. Default: FALSE.

Internals

```
Calls torch::nn_relu6() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchReLU6
```

Methods

Public methods:

- PipeOpTorchReLU6\$new()
- PipeOpTorchReLU6\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchReLU6$new(id = "nn_relu6", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchReLU6$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

wise be set during construction.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_reshape,
```

```
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_relu6")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_reshape
```

Reshape a Tensor

Description

Reshape a tensor to the given shape.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

• shape :: integer(1)

The desired output shape. Unknown dimension (one at most) can either be specified as -1 or NA.

Internals

Calls nn_reshape() when trained. This internally calls torch::torch_reshape() with the given shape.

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchReshape
```

Methods

Public methods:

- PipeOpTorchReshape\$new()
- PipeOpTorchReshape\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchReshape$new(id = "nn_reshape", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchReshape$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

140 mlr_pipeops_nn_rrelu

Examples

```
# Construct the PipeOp
pipeop = po("nn_reshape")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_rrelu RReLU Activation Function
```

Description

Randomized leaky ReLU.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• lower:: numeric(1)
Lower bound of the uniform distribution. Default: 1/8.
```

```
• upper:: numeric(1)
Upper bound of the uniform distribution. Default: 1/3.
```

```
• inplace :: logical(1)
Whether to do the operation in-place. Default: FALSE.
```

Internals

```
Calls torch::nn_rrelu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchRReLU
```

141

Methods

Public methods:

- PipeOpTorchRReLU\$new()
- PipeOpTorchRReLU\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchRReLU$new(id = "nn_rrelu", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchRReLU$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_rrelu")
pipeop
# The available parameters
pipeop$param_set
```

142 mlr_pipeops_nn_selu

```
mlr_pipeops_nn_selu SELU Activation Function
```

Description

Applies element-wise,

```
SELU(x) = scale * (max(0, x) + min(0, \alpha * (exp(x) - 1)))
```

, with $\alpha=1.6732632423543772848170429916717$ and scale=1.0507009873554804934193349852946.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• inplace :: logical(1)
Whether to do the operation in-place. Default: FALSE.
```

Internals

```
Calls torch::nn_selu() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSELU
```

Methods

Public methods:

- PipeOpTorchSELU\$new()
- PipeOpTorchSELU\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchSELU$new(id = "nn_selu", param_vals = list())
Arguments:
```

```
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchSELU$clone(deep = FALSE)
Arguments:
```

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax,
mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_selu")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_sigmoid
```

Sigmoid Activation Function

Description

```
Applies element-wise Sigmoid(x_i) = \frac{1}{1 + exp(-x_i)}
```

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

```
Calls torch::nn_sigmoid() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSigmoid
```

Methods

Public methods:

- PipeOpTorchSigmoid\$new()
- PipeOpTorchSigmoid\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchSigmoid$new(id = "nn_sigmoid", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchSigmoid$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_sigmoid")
pipeop
# The available parameters
pipeop$param_set
```

Description

Applies a softmax function.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

dim:: integer(1)
 A dimension along which Softmax will be computed (so every slice along dim will sum to 1).

Internals

```
Calls torch::nn_softmax() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSoftmax
```

Methods

Public methods:

- PipeOpTorchSoftmax\$new()
- PipeOpTorchSoftmax\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchSoftmax$new(id = "nn_softmax", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchSoftmax$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

wise be set during construction.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
```

```
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_softmax")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_softplus
```

SoftPlus Activation Function

Description

Applies element-wise, the function $Softplus(x) = 1/\beta * log(1 + exp(\beta * x)).$

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• beta :: numeric(1)

The beta value for the Softplus formulation. Default: 1
```

```
• threshold :: numeric(1)
Values above this revert to a linear function. Default: 20
```

Internals

```
Calls torch::nn_softplus() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSoftPlus
```

Methods

Public methods:

- PipeOpTorchSoftPlus\$new()
- PipeOpTorchSoftPlus\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchSoftPlus$new(id = "nn_softplus", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchSoftPlus$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze,
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_softplus")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_softshrink
```

Soft Shrink Activation Function

Description

Applies the soft shrinkage function elementwise

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

```
• lamd :: numeric(1)
The lambda (must be no less than zero) value for the Softshrink formulation. Default: 0.5
```

Internals

```
Calls torch::nn_softshrink() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSoftShrink
```

Methods

Public methods:

- PipeOpTorchSoftShrink\$new()
- PipeOpTorchSoftShrink\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchSoftShrink$new(id = "nn_softshrink", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchSoftShrink$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
\verb|mlr_pipeops_nn_softmax|, \verb|mlr_pipeops_nn_softplus|, \verb|mlr_pipeops_nn_softsign|, \| mlr_pipeops_nn_softsign|, \| 
mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_softshrink")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_softsign
```

SoftSign Activation Function

Description

Applies element-wise, the function SoftSign(x) = x/(1 + |x|)

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

```
Calls torch::nn_softsign() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSoftSign
```

Methods

Public methods:

- PipeOpTorchSoftSign\$new()
- PipeOpTorchSoftSign\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchSoftSign$new(id = "nn_softsign", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
```

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

PipeOpTorchSoftSign\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_softsign")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_squeeze
```

Squeeze a Tensor

Description

Squeezes a tensor by calling torch::torch_squeeze() with the given dimension dim.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

• dim::integer(1)

The dimension to squeeze. If NULL, all dimensions of size 1 will be squeezed. Negative values are interpreted downwards from the last dimension.

Internals

```
Calls nn_squeeze() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchSqueeze
```

Methods

Public methods:

- PipeOpTorchSqueeze\$new()
- PipeOpTorchSqueeze\$clone()

Method new(): Creates a new instance of this R6 class.

```
PipeOpTorchSqueeze$new(id = "nn_squeeze", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
```

param_vals (list())

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

```
PipeOpTorchSqueeze$clone(deep = FALSE)
```

Arguments:

deep Whether to make a deep clone.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_squeeze")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_tanh

Tanh Activation Function

Description

Applies the element-wise function:

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

mlr_pipeops_nn_tanh 155

Parameters

No parameters.

Internals

```
Calls torch::nn_tanh() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchTanh
```

Methods

Public methods:

- PipeOpTorchTanh\$new()
- PipeOpTorchTanh\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchTanh$new(id = "nn_tanh", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchTanh$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
```

```
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_tanh")
pipeop
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_tanhshrink

Tanh Shrink Activation Function

Description

Applies element-wise, Tanhshrink(x) = x - Tanh(x)

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

No parameters.

Internals

```
Calls torch::nn_tanhshrink() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchTanhShrink
```

Methods

Public methods:

- PipeOpTorchTanhShrink\$new()
- PipeOpTorchTanhShrink\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchTanhShrink$new(id = "nn_tanhshrink", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchTanhShrink$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_tanhshrink")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_nn_threshold
```

Treshold Activation Function

Description

Thresholds each element of the input Tensor.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

- threshold :: numeric(1)
 The value to threshold at.
- value :: numeric(1)
 The value to replace with.
- inplace :: logical(1)
 Can optionally do the operation in-place. Default: 'FALSE'.

Internals

```
Calls torch::nn_threshold() when trained.
```

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchThreshold
```

Methods

Public methods:

- PipeOpTorchThreshold\$new()
- PipeOpTorchThreshold\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchThreshold$new(id = "nn_threshold", param_vals = list())
```

```
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
    wise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchThreshold$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_unsqueeze,
mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
```

Examples

```
# Construct the PipeOp
pipeop = po("nn_threshold", threshold = 1, value = 2)
# The available parameters
pipeop$param_set
```

mlr_pipeops_nn_unsqueeze

Unqueeze a Tensor

Description

```
Unqueeze a Tensor
Unqueeze a Tensor
```

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method \$shapes_out().

Credit

Part of this documentation have been copied or adapted from the documentation of torch.

Parameters

dim:: integer(1)
 The dimension which to unsqueeze. Negative values are interpreted downwards from the last dimension.

Internals

Calls nn_unsqueeze() when trained. This internally calls torch::torch_unsqueeze().

Super classes

```
mlr3pipelines::PipeOp -> mlr3torch::PipeOpTorch -> PipeOpTorchUnsqueeze
```

Methods

Public methods:

- PipeOpTorchUnsqueeze\$new()
- PipeOpTorchUnsqueeze\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchUnsqueeze$new(id = "nn_unsqueeze", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that value is a set of the settings.
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchUnsqueeze$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model mlr_pipeops_torch_model_regr

Examples

```
# Construct the PipeOp
pipeop = po("nn_unsqueeze")
pipeop
# The available parameters
pipeop$param_set
```

```
mlr_pipeops_preproc_torch
```

Base Class for Lazy Tensor Preprocessing

Description

This PipeOp can be used to preprocess (one or more) lazy_tensor columns contained in an mlr3::Task. The preprocessing function is specified as construction argument fn and additional arguments to this function can be defined through the PipeOp's parameter set. The preprocessing is done per column, i.e. the number of lazy tensor output columns is equal to the number of lazy tensor input columns.

To create custom preprocessing PipeOps you can use pipeop_preproc_torch.

Inheriting

In addition to specifying the construction arguments, you can overwrite the private . shapes_out() method. If you don't overwrite it, the output shapes are assumed to be unknown (NULL).

• .shapes_out(shapes_in, param_vals, task)
(list(), list(), TaskorNULL) -> list()\cr This private method calculates the output shapes of the lazy
This private method only has the responsibility to calculate the output shapes for one input
column, i.e. the input shapes_in can be assumed to have exactly one shape vector for which
it must calculate the output shapes and return it as a list() of length 1. It can also be assumed
that the shape is not NULL (i.e. unknown). Also, the first dimension can be NA, i.e. is unknown
(as for the batch dimension).

Input and Output Channels

See PipeOpTaskPreproc.

State

In addition to state elements from PipeOpTaskPreprocSimple, the state also contains the \$param_vals that were set during training.

Parameters

In addition to the parameters inherited from PipeOpTaskPreproc as well as those specified during construction as the argument param_set there are the following parameters:

• stages :: character(1)

The stages during which to apply the preprocessing. Can be one of "train", "predict" or "both". The initial value of this parameter is set to "train" when the PipeOp's id starts with "augment_" and to "both" otherwise. Note that the preprocessing that is applied during \$predict() uses the parameters that were set during \$train() and not those that are set when performing the prediction.

Internals

During \$train() / \$predict(), a PipeOpModule with one input and one output channel is created. The pipeop applies the function fn to the input tensor while additionally passing the parameter values (minus stages and affect_columns) to fn. The preprocessing graph of the lazy tensor columns is shallowly cloned and the PipeOpModule is added. This is done to avoid modifying user input and means that identical PipeOpModules can be part of different preprocessing graphs. This is only possible, because the created PipeOpModule is stateless.

At a later point in the graph, preprocessing graphs will be merged if possible to avoid unnecessary computation. This is best illustrated by example: One lazy tensor column's preprocessing graph is $A \rightarrow B$. Then, two branches are created $B \rightarrow C$ and $B \rightarrow D$, creating two preprocessing graphs $A \rightarrow B \rightarrow C$ and $A \rightarrow B \rightarrow D$. When loading the data, we want to run the preprocessing only once, i.e. we don't want to run the $A \rightarrow B$ part twice. For this reason, task_dataset() will try to merge graphs and cache results from graphs. However, only graphs using the same dataset can currently be merged.

Also, the shapes created during \$train() and \$predict() might differ. To avoid the creation of graphs where the predict shapes are incompatible with the train shapes, the hypothetical predict shapes are already calculated during \$train() (this is why the parameters that are set during train are also used during predict) and the PipeOpTorchModel will check the train and predict shapes for compatibility before starting the training.

Otherwise, this mechanism is very similar to the ModelDescriptor construct.

Super classes

```
mlr3pipelines::PipeOp->mlr3pipelines::PipeOpTaskPreproc->PipeOpTaskPreprocTorch
```

Active bindings

fn The preprocessing function.

rowwise Whether the preprocessing is applied rowwise.

Methods

Public methods:

- PipeOpTaskPreprocTorch\$new()
- PipeOpTaskPreprocTorch\$shapes_out()
- PipeOpTaskPreprocTorch\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTaskPreprocTorch$new(
   fn,
   id = "preproc_torch",
   param_vals = list(),
   param_set = ps(),
   packages = character(0),
   rowwise = FALSE,
   stages_init = NULL,
   tags = NULL
)
Arguments:
fn (function or character(2))
```

The preprocessing function. Must not modify its input in-place. If it is a character(2), the first element should be the namespace and the second element the name. When the preprocessing function is applied to the tensor, the tensor will be passed by position as the first argument. If the param_set is inferred (left as NULL) it is assumed that the first argument is the torch_tensor.

```
id (character(1))
    The id for of the new object.
param_vals (named list())
    Parameter values to be set after construction.
```

```
param_set (ParamSet)
     In case the function fn takes additional parameter besides a torch_tensor they can be
     specified as parameters. None of the parameters can have the "predict" tag. All tags
     should include "train".
 packages (character())
     The packages the preprocessing function depends on.
 rowwise (logical(1))
     Whether the preprocessing function is applied rowwise (and then concatenated by row) or
     directly to the whole tensor. In the first case there is no batch dimension.
 stages_init (character(1))
     Initial value for the stages parameter.
 tags (character())
     Tags for the pipeop.
Method shapes_out(): Calculates the output shapes that would result in applying the prepro-
cessing to one or more lazy tensor columns with the provided shape. Names are ignored and only
order matters. It uses the parameter values that are currently set.
 Usage:
 PipeOpTaskPreprocTorch$shapes_out(shapes_in, stage = NULL, task = NULL)
 Arguments:
 shapes_in (list() of (integer() or NULL))
     The input input shapes of the lazy tensors. NULL indicates that the shape is unknown. First
     dimension must be NA (if it is not NULL).
 stage (character(1))
     The stage: either "train" or "predict".
 task (Task or NULL)
```

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTaskPreprocTorch\$clone(deep = FALSE)

The task, which is very rarely needed.

*Returns: list() of (integer() or NULL)

Arguments:

deep Whether to make a deep clone.

Examples

```
# Creating a simple task
d = data.table(
    x1 = as_lazy_tensor(rnorm(10)),
    x2 = as_lazy_tensor(rnorm(10)),
    x3 = as_lazy_tensor(as.double(1:10)),
    y = rnorm(10)
)
taskin = as_task_regr(d, target = "y")
```

```
# Creating a simple preprocessing pipeop
po_simple = po("preproc_torch",
  # get rid of environment baggage
  fn = mlr3misc::crate(function(x, a) x + a),
  param_set = paradox::ps(a = paradox::p_int(tags = c("train", "required")))
)
po_simple$param_set$set_values(
  a = 100,
  affect_columns = selector_name(c("x1", "x2")),
  stages = "both" # use during train and predict
)
taskout_train = po_simple$train(list(taskin))[[1L]]
materialize(taskout_train$data(cols = c("x1", "x2")), rbind = TRUE)
taskout_predict_noaug = po_simple$predict(list(taskin))[[1L]]
materialize(taskout_predict_noaug$data(cols = c("x1", "x2")), rbind = TRUE)
po_simple$param_set$set_values(
  stages = "train"
# transformation is not applied
taskout_predict_aug = po_simple$predict(list(taskin))[[1L]]
materialize(taskout_predict_aug$data(cols = c("x1", "x2")), rbind = TRUE)
# Creating a more complex preprocessing PipeOp
PipeOpPreprocTorchPoly = R6::R6Class("PipeOpPreprocTorchPoly",
 inherit = PipeOpTaskPreprocTorch,
 public = list(
   initialize = function(id = "preproc_poly", param_vals = list()) {
     param_set = paradox::ps(
       n_degree = paradox::p_int(lower = 1L, tags = c("train", "required"))
     param_set$set_values(
       n_{degree} = 1L
     fn = mlr3misc::crate(function(x, n_degree) {
       torch::torch_cat(
         lapply(seq_len(n_degree), function(d) torch::torch_pow(x, d)),
         dim = 2L
       )
     })
     super$initialize(
       fn = fn,
       id = id,
       packages = character(0),
       param_vals = param_vals,
       param_set = param_set,
       stages_init = "both"
```

```
}
 ),
 private = list(
   .shapes_out = function(shapes_in, param_vals, task) {
     # shapes_in is a list of length 1 containing the shapes
     checkmate::assert_true(length(shapes_in[[1L]]) == 2L)
     if (shapes_in[[1L]][2L] != 1L) {
      stop("Input shape must be (NA, 1)")
     list(c(NA, param_vals$n_degree))
   }
)
po_poly = PipeOpPreprocTorchPoly$new(
 param_vals = list(n_degree = 3L, affect_columns = selector_name("x3"))
po_poly$shapes_out(list(c(NA, 1L)), stage = "train")
taskout = po_poly$train(list(taskin))[[1L]]
materialize(taskout$data(cols = "x3"), rbind = TRUE)
```

mlr_pipeops_torch

Base Class for Torch Module Constructor Wrappers

Description

PipeOpTorch is the base class for all PipeOps that represent neural network layers in a Graph. During **training**, it generates a PipeOpModule that wraps an nn_module and attaches it to the architecture, which is also represented as a Graph consisting mostly of PipeOpModules an PipeOpNOPs.

While the former Graph operates on ModelDescriptors, the latter operates on tensors.

The relationship between a PipeOpTorch and a PipeOpModule is similar to the relationshop between a nn_module_generator (like nn_linear) and a nn_module (like the output of nn_linear(...)). A crucial difference is that the PipeOpTorch infers auxiliary parameters (like in_features for nn_linear) automatically from the intermediate tensor shapes that are being communicated through the ModelDescriptor.

During **prediction**, PipeOpTorch takes in a Task in each channel and outputs the same new Task resulting from their feature union in each channel. If there is only one input and output channel, the task is simply piped through.

Inheriting

When inheriting from this class, one should overload either the private\$.shapes_out() and the private\$.shape_dependent_params() methods, or overload private\$.make_module().

.make_module(shapes_in, param_vals, task)
 (list(), list()) -> nn_module
 This private method is called to generated the nn_module that is passed as argument module to
 PipeOpModule. It must be overwritten, when no module_generator is provided. If left as is,
 it calls the provided module_generator with the arguments obtained by the private method
 .shape_dependent_params().

- .shapes_out(shapes_in, param_vals, task)
 (list(), list(), Task or NULL) -> named list()
 This private method gets a list of numeric vectors (shapes_in), the parameter values (param_vals), as well as an (optional) Task. The shapes_in can be assumed to be in the same order as the input names of the PipeOp. The output shapes must be in the same order as the output names of the PipeOp. In case the output shapes depends on the task (as is the case for PipeOpTorchHead), the function should return valid output shapes (possibly containing NAs) if the task argument is provided or not.
- .shape_dependent_params(shapes_in, param_vals, task)
 (list(), list()) -> named list()
 This private method has the same inputs as .shapes_out. If .make_module() is not overwritten, it constructs the arguments passed to module_generator. Usually this means that it must infer the auxiliary parameters that can be inferred from the input shapes and add it to the user-supplied parameter values (param_vals).

Input and Output Channels

During *training*, all inputs and outputs are of class ModelDescriptor. During *prediction*, all input and output channels are of class Task.

State

The state is the value calculated by the public method shapes_out().

Parameters

The ParamSet is specified by the child class inheriting from PipeOpTorch. Usually the parameters are the arguments of the wrapped nn_module minus the auxiliary parameter that can be automatically inferred from the shapes of the input tensors.

Internals

During training, the PipeOpTorch creates a PipeOpModule for the given parameter specification and the input shapes from the incoming ModelDescriptors using the private method .make_module(). The input shapes are provided by the slot pointer_shape of the incoming ModelDescriptors. The channel names of this PipeOpModule are identical to the channel names of the generating PipeOpTorch.

A model descriptor union of all incoming ModelDescriptors is then created. Note that this modifies the graph of the first ModelDescriptor in place for efficiency. The PipeOpModule is added to the graph slot of this union and the edges that connect the sending PipeOpModules to the input channel of this PipeOpModule are addeded to the graph. This is possible because every incoming ModelDescriptor contains the information about the id and the channel name of the sending PipeOp in the slot pointer.

The new graph in the model_descriptor_union represents the current state of the neural network architecture. It is structurally similar to the subgraph that consists of all pipeops of class PipeOpTorch and PipeOpTorchIngress that are ancestors of this PipeOpTorch.

For the output, a shallow copy of the ModelDescriptor is created and the pointer and pointer_shape are updated accordingly. The shallow copy means that all ModelDescriptors point to the same Graph which allows the graph to be modified by-reference in different parts of the code.

Super class

```
mlr3pipelines::PipeOp -> PipeOpTorch
```

Public fields

```
module_generator (nn_module_generator or NULL)
```

The module generator wrapped by this PipeOpTorch. If NULL, the private method private\$.make_module(shapes_in param_vals) must be overwritte, see section 'Inheriting'. Do not change this after construction.

Methods

Public methods:

- PipeOpTorch\$new()
- PipeOpTorch\$shapes_out()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorch$new(
  id,
  module_generator,
  param_set = ps(),
  param_vals = list(),
  inname = "input",
  outname = "output"
  packages = "torch",
  tags = NULL
Arguments:
id (character(1))
   Identifier of the resulting object.
module_generator (nn_module_generator)
   The torch module generator.
param_set (ParamSet)
   The parameter set.
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

```
inname (character())
```

The names of the PipeOp's input channels. These will be the input channels of the generated PipeOpModule. Unless the wrapped module_generator's forward method (if present) has the argument ..., inname must be identical to those argument names in order to avoid any ambiguity.

If the forward method has the argument . . . , the order of the input channels determines how the tensors will be passed to the wrapped nn_module.

If left as NULL (default), the argument module_generator must be given and the argument names of the modue_generator's forward function are set as inname.

```
outname (character())
```

The names of the output channels channels. These will be the ouput channels of the generated PipeOpModule and therefore also the names of the list returned by its \$train(). In case there is more than one output channel, the nn_module that is constructed by this PipeOp during training must return a named list(), where the names of the list are the names out the output channels. The default is "output".

```
packages (character())
```

The R packages this object depends on.

```
tags (character())
```

The tags of the PipeOp. The tags "torch" is always added.

Method shapes_out(): Calculates the output shapes for the given input shapes, parameters and task.

```
Usage:
```

```
PipeOpTorch$shapes_out(shapes_in, task = NULL)
```

Arguments:

```
shapes_in (list() of integer())
```

The input input shapes, which must be in the same order as the input channel names of the PipeOp.

```
task (Task or NULL)
```

The task, which is very rarely used (default is NULL). An exception is PipeOpTorchHead.

Returns: A named list() containing the output shapes. The names are the names of the output channels of the PipeOp.

See Also

```
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()
```

Examples

```
## Creating a neural network
# In torch

task = tsk("iris")
network_generator = torch::nn_module(
```

```
initialize = function(task, d_hidden) {
   d_in = length(task$feature_names)
    self$linear = torch::nn_linear(d_in, d_hidden)
    self$output = if (task$task_type == "regr") {
      torch::nn_linear(d_hidden, 1)
    } else if (task$task_type == "classif") {
      torch::nn_linear(d_hidden, length(task$class_names))
   }
  },
  forward = function(x) {
   x = self linear(x)
   x = torch::nnf_relu(x)
   self$output(x)
 }
)
network = network_generator(task, d_hidden = 50)
x = torch::torch_tensor(as.matrix(task$data(1, task$feature_names)))
y = torch::with_no_grad(network(x))
# In mlr3torch
network_generator = po("torch_ingress_num") %>>%
  po("nn_linear", out_features = 50) %>>%
  po("nn_head")
md = network_generator$train(task)[[1L]]
network = model_descriptor_to_module(md)
y = torch::with_no_grad(network(torch_ingress_num.input = x))
## Implementing a custom PipeOpTorch
# defining a custom module
nn_custom = nn_module("nn_custom",
  initialize = function(d_in1, d_in2, d_out1, d_out2, bias = TRUE) {
    self$linear1 = nn_linear(d_in1, d_out1, bias)
    self$linear2 = nn_linear(d_in2, d_out2, bias)
  forward = function(input1, input2) {
    output1 = self$linear1(input1)
   output2 = self$linear1(input2)
   list(output1 = output1, output2 = output2)
  }
)
# wrapping the module into a custom PipeOpTorch
library(paradox)
PipeOpTorchCustom = R6::R6Class("PipeOpTorchCustom",
  inherit = PipeOpTorch,
```

```
public = list(
    initialize = function(id = "nn_custom", param_vals = list()) {
     param_set = ps(
        d_out1 = p_int(lower = 1, tags = c("required", "train")),
        d_out2 = p_int(lower = 1, tags = c("required", "train")),
        bias = p_lgl(default = TRUE, tags = "train")
      super$initialize(
        id = id,
        param_vals = param_vals,
        param_set = param_set,
        inname = c("input1", "input2"),
        outname = c("output1", "output2"),
        module_generator = nn_custom
     )
   }
 ),
 private = list(
    .shape_dependent_params = function(shapes_in, param_vals, task) {
     list(d_in1 = tail(shapes_in[["input1"]], 1)), d_in2 = tail(shapes_in[["input2"]], 1)
     )
    },
    .shapes_out = function(shapes_in, param_vals, task) {
     list(
        input1 = c(head(shapes_in[["input1"]], -1), param_vals$d_out1),
        input2 = c(head(shapes_in[["input2"]], -1), param_vals$d_out2)
     )
   }
 )
)
## Training
# generate input
task = tsk("iris")
task1 = task$clone()$select(paste0("Sepal.", c("Length", "Width")))
task2 = task$clone()$select(paste0("Petal.", c("Length", "Width")))
graph = gunion(list(po("torch_ingress_num_1"), po("torch_ingress_num_2")))
mds_in = graph$train(list(task1, task2), single_input = FALSE)
mds_in[[1L]][c("graph", "task", "ingress", "pointer", "pointer_shape")]
mds_in[[2L]][c("graph", "task", "ingress", "pointer", "pointer_shape")]
# creating the PipeOpTorch and training it
po_torch = PipeOpTorchCustom$new()
po_torch$param_set$values = list(d_out1 = 10, d_out2 = 20)
train_input = list(input1 = mds_in[[1L]], input2 = mds_in[[2L]])
mds_out = do.call(po_torch$train, args = list(input = train_input))
po_torch$state
# the new model descriptors
```

```
# the resulting graphs are identical
identical(mds_out[[1L]]$graph, mds_out[[2L]]$graph)
# not that as a side-effect, also one of the input graphs is modified in-place for efficiency
mds_in[[1L]]$graph$edges
# The new task has both Sepal and Petal features
identical(mds_out[[1L]]$task, mds_out[[2L]]$task)
mds_out[[2L]]$task
# The new ingress slot contains all ingressors
identical(mds_out[[1L]]$ingress, mds_out[[2L]]$ingress)
mds_out[[1L]]$ingress
# The pointer and pointer_shape slots are different
mds_out[[1L]]$pointer
mds_out[[2L]]$pointer
mds_out[[1L]]$pointer_shape
mds_out[[2L]]$pointer_shape
## Prediction
predict_input = list(input1 = task1, input2 = task2)
tasks_out = do.call(po_torch$predict, args = list(input = predict_input))
identical(tasks_out[[1L]], tasks_out[[2L]])
```

Description

Configures the callbacks of a deep learning model.

Input and Output Channels

There is one input channel "input" and one output channel "output". During *training*, the channels are of class ModelDescriptor. During *prediction*, the channels are of class Task.

State

The state is the value calculated by the public method shapes_out().

Parameters

The parameters are defined dynamically from the callbacks, where the id of the respective callbacks is the respective set id.

Internals

During training the callbacks are cloned and added to the ModelDescriptor.

Super class

```
mlr3pipelines::PipeOp -> PipeOpTorchCallbacks
```

Methods

Public methods:

- PipeOpTorchCallbacks\$new()
- PipeOpTorchCallbacks\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchCallbacks$new(
   callbacks = list(),
   id = "torch_callbacks",
   param_vals = list()
)

Arguments:
callbacks (list of TorchCallbacks)
   The callbacks (or something convertible via as_torch_callbacks()). Must have unique ids. All callbacks are cloned during construction.
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchCallbacks$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other Model Configuration: ModelDescriptor(), mlr_pipeops_torch_loss, mlr_pipeops_torch_optimizer, model_descriptor_union()

Other PipeOp: mlr_pipeops_module, mlr_pipeops_torch_optimizer
```

Examples

```
po_cb = po("torch_callbacks", "checkpoint")
po_cb$param_set
mdin = po("torch_ingress_num")$train(list(tsk("iris")))
mdin[[1L]]$callbacks
mdout = po_cb$train(mdin)[[1L]]
mdout$callbacks
# Can be called again
po_cb1 = po("torch_callbacks", t_clbk("progress"))
mdout1 = po_cb1$train(list(mdout))[[1L]]
mdout1$callbacks
```

```
mlr_pipeops_torch_ingress
```

Entrypoint to Torch Network

Description

Use this as entry-point to mlr3torch-networks. Unless you are an advanced user, you should not need to use this directly but PipeOpTorchIngressNumeric, PipeOpTorchIngressCategorical or PipeOpTorchIngressLazyTensor.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is set to the input shape.

Parameters

Defined by the construction argument param_set.

Internals

Creates an object of class TorchIngressToken for the given task. The purpuse of this is to store the information on how to construct the torch dataloader from the task for this entry point of the network.

Super class

```
mlr3pipelines::PipeOp -> PipeOpTorchIngress
```

Active bindings

```
feature_types (character(1))
```

The features types that can be consumed by this PipeOpTorchIngress.

Methods

Public methods:

- PipeOpTorchIngress\$new()
- PipeOpTorchIngress\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchIngress$new(
  id,
  param_set = ps(),
  param_vals = list(),
  packages = character(0),
  feature_types
Arguments:
id (character(1))
   Identifier of the resulting object.
param_set (ParamSet)
   The parameter set.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would other-
   wise be set during construction.
packages (character())
   The R packages this object depends on.
feature_types (character())
   The feature types. See mlr_reflections$task_feature_types for available values, Ad-
   ditionally, "lazy_tensor" is supported.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchIngress$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
```

```
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_softmax, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model_regr
```

Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltns: mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()

```
mlr_pipeops_torch_ingress_categ
```

Torch Entry Point for Categorical Features

Description

Ingress PipeOp that represents a categorical (factor(), ordered() and logical()) entry point to a torch network.

Parameters

• select :: logical(1)
Whether PipeOp should selected the supported feature types. Otherwise it will err on receiving tasks with unsupported feature types.

Internals

Uses batchgetter_categ().

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is set to the input shape.

Super classes

mlr3pipelines::Pipe0p->mlr3torch::Pipe0pTorchIngress->Pipe0pTorchIngressCategorical

Methods

Public methods:

- PipeOpTorchIngressCategorical\$new()
- PipeOpTorchIngressCategorical\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchIngressCategorical$new(
   id = "torch_ingress_categ",
   param_vals = list()
)
Arguments:
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchIngressCategorical\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

model_descriptor_union(), nn_graph()

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_mode
mlr_pipeops_torch_model_regr
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model,
mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_ltnsr,
mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(),
```

Examples

```
graph = po("select", selector = selector_type("factor")) %>>%
    po("torch_ingress_categ")
task = tsk("german_credit")
# The output is a model descriptor
md = graph$train(task)[[1L]]
ingress = md$ingress[[1L]]
ingress$batchgetter(task$data(1, ingress$features), "cpu")
```

Description

Ingress for a single lazy_tensor column.

Parameters

• shape :: integer()
The shape of the tensor, where the first dimension (batch) must be NA. When it is not specified, the lazy tensor input column needs to have a known shape.

Internals

The returned batchgetter materializes the lazy tensor column to a tensor.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is set to the input shape.

Super classes

```
mlr3pipelines::Pipe0p->mlr3torch::Pipe0pTorchIngress->Pipe0pTorchIngressLazyTensor
```

Methods

Public methods:

- PipeOpTorchIngressLazyTensor\$new()
- PipeOpTorchIngressLazyTensor\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchIngressLazyTensor$new(
   id = "torch_ingress_ltnsr",
   param_vals = list()
)

Arguments:
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:
```

PipeOpTorchIngressLazyTensor\$clone(deep = FALSE)

deep Whether to make a deep clone.

See Also

Arguments:

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model, mlr_pipeops_torch_model
mlr_pipeops_torch_model_regr
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model,
mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
```

mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(),

Examples

```
po_ingress = po("torch_ingress_ltnsr")
task = tsk("lazy_iris")
md = po_ingress$train(list(task))[[1L]]
```

model_descriptor_union(), nn_graph()

```
ingress = md$ingress
x_{\text{batch}} = ingress[[1L]]$batchgetter(data = task$data(1, "x"), device = "cpu", cache = NULL)
# Now we try a lazy tensor with unknown shape, i.e. the shapes between the rows can differ
ds = dataset(
 initialize = function() self$x = list(torch_randn(3, 10, 10), torch_randn(3, 8, 8)),
  .getitem = function(i) list(x = self$x[[i]]),
  .length = function() 2)()
task_unknown = as_task_regr(data.table(
 x = as_{lazy_{tensor}(ds, dataset_{shapes} = list(x = NULL)),
 y = rnorm(2)
), target = "y", id = "example2")
# this task (as it is) can NOT be processed by PipeOpTorchIngressLazyTensor
# It therefore needs to be preprocessed
po_resize = po("trafo_resize", size = c(6, 6))
task_unknown_resize = po_resize$train(list(task_unknown))[[1L]]
# printing the transformed column still shows unknown shapes,
# because the preprocessing pipeop cannot infer them,
# however we know that the shape is now (3, 10, 10) for all rows
task_unknown_resize$data(1:2, "x")
po_ingress$param_set$set_values(shape = c(NA, 3, 6, 6))
md2 = po_ingress$train(list(task_unknown_resize))[[1L]]
ingress2 = md2$ingress
x_batch2 = ingress2[[1L]]$batchgetter(
 data = task_unknown_resize$data(1:2, "x"),
 device = "cpu",
 cache = NULL
)
x_batch2
```

```
mlr_pipeops_torch_ingress_num
```

Torch Entry Point for Numeric Features

Description

Ingress PipeOp that represents a numeric (integer() and numeric()) entry point to a torch network.

Internals

Uses batchgetter_num().

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is set to the input shape.

Super classes

mlr3pipelines::Pipe0p->mlr3torch::Pipe0pTorchIngress->Pipe0pTorchIngressNumeric

Methods

Public methods:

- PipeOpTorchIngressNumeric\$new()
- PipeOpTorchIngressNumeric\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

PipeOpTorchIngressNumeric\$new(id = "torch_ingress_num", param_vals = list())

Arguments:

id (character(1))

Identifier of the resulting object.

param_vals (list())

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

Usage:

PipeOpTorchIngressNumeric\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()
```

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,

```
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relud,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_loss, mlr_pipeops_torch_model,
mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Examples

```
graph = po("select", selector = selector_type(c("numeric", "integer"))) %>>%
   po("torch_ingress_num")
task = tsk("german_credit")
# The output is a model descriptor
md = graph$train(task)[[1L]]
ingress = md$ingress[[1L]]
ingress$batchgetter(task$data(1:5, ingress$features), "cpu")
```

```
mlr_pipeops_torch_loss

Loss Configuration
```

Description

Configures the loss of a deep learning model.

Input and Output Channels

One input channel called "input" and one output channel called "output". For an explanation see PipeOpTorch.

State

The state is the value calculated by the public method shapes_out().

Parameters

The parameters are defined dynamically from the loss set during construction.

Internals

During training the loss is cloned and added to the ModelDescriptor.

Super class

```
mlr3pipelines::PipeOp -> PipeOpTorchLoss
```

Methods

Public methods:

- PipeOpTorchLoss\$new()
- PipeOpTorchLoss\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchLoss$new(loss, id = "torch_loss", param_vals = list())
Arguments:
loss (TorchLoss or character(1) or nn_loss)
    The loss (or something convertible via as_torch_loss()).
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

wise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchLoss$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_softmax, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
```

```
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_model,
mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr
```

Other Model Configuration: ModelDescriptor(), mlr_pipeops_torch_callbacks, mlr_pipeops_torch_optimizer, model_descriptor_union()

Examples

```
po_loss = po("torch_loss", loss = t_loss("cross_entropy"))
po_loss$param_set
mdin = po("torch_ingress_num")$train(list(tsk("iris")))
mdin[[1L]]$loss
mdout = po_loss$train(mdin)[[1L]]
mdout$loss
```

```
mlr_pipeops_torch_model
```

PipeOp Torch Model

Description

Builds a Torch Learner from a ModelDescriptor and trains it with the given parameter specification. The task type must be specified during construction.

Input and Output Channels

There is one input channel "input" that takes in ModelDescriptor during training and a Task of the specified task_type during prediction. The output is NULL during training and a Prediction of given task_type during prediction.

State

A trained LearnerTorchModel.

Parameters

General:

The parameters of the optimizer, loss and callbacks, prefixed with "opt.", "loss." and "cb.<callback id>." respectively, as well as:

```
• epochs :: integer(1)
The number of epochs.
```

```
• device :: character(1)

The device. One of "auto", "cpu", or "cuda" or other values defined in mlr_reflections$torch$devices.

The value is initialized to "auto", which will select "cuda" if possible, then try "mps" and otherwise fall back to "cpu".
```

- num_threads :: integer(1)

 The number of threads for intraop pararallelization (if device is "cpu"). This value is initialized to 1.
- seed :: integer(1) or "random" or NULL

The torch seed that is used during training and prediction. This value is initialized to "random", which means that a random seed will be sampled at the beginning of the training phase. This seed (either set or randomly sampled) is available via \$model\$seed after training and used during prediction. Note that by setting the seed during the training phase this will mean that by default (i.e. when seed is "random"), clones of the learner will use a different seed. If set to NULL, no seeding will be done.

Evaluation:

- measures_train :: Measure or list() of Measures. Measures to be evaluated during training.
- measures_valid :: Measure or list() of Measures.

 Measures to be evaluated during validation.
- eval_freq :: integer(1)

 How often the train / validation predictions are evaluated using measures_train / measures_valid.

 This is initialized to 1. Note that the final model is always evaluated.

Early Stopping:

• patience :: integer(1)

This activates early stopping using the validation scores. If the performance of a model does not improve for patience evaluation steps, training is ended. Note that the final model is stored in the learner, not the best model. This is initialized to 0, which means no early stopping. The first entry from measures_valid is used as the metric. This also requires to specify the \$validate field of the Learner, as well as measures_valid.

min_delta:: double(1)
 The minimum improvement threshold (>) for early stopping. Is initialized to 0.

Dataloader:

- batch_size :: integer(1)
 The batch size (required).
- shuffle :: logical(1)

Whether to shuffle the instances in the dataset. Default is FALSE. This does not impact validation.

- sampler :: torch::sampler
 Object that defines how the dataloader draw samples.
- batch_sampler :: torch::sampler
 Object that defines how the dataloader draws batches.
- num_workers :: integer(1)

 The number of workers for data loading (batches are loaded in parallel). The default is 0, which means that data will be loaded in the main process.
- collate_fn :: function How to merge a list of samples to form a batch.

- pin_memory :: logical(1)
 Whether the dataloader copies tensors into CUDA pinned memory before returning them.
- drop_last :: logical(1)
 Whether to drop the last training batch in each epoch during training. Default is FALSE.
- timeout :: numeric(1)
 The timeout value for collecting a batch from workers. Negative values mean no timeout and the default is -1.
- worker_init_fn:: function(id)
 A function that receives the worker id (in [1, num_workers]) and is exectued after seeding on the worker but before data loading.
- worker_globals :: list() | character()
 When loading data in parallel, this allows to export globals to the workers. If this is a character vector, the objects in the global environment with those names are copied to the workers.
- worker_packages :: character()
 Which packages to load on the workers.

Also see torch::dataloder for more information.

Internals

A LearnerTorchModel is created by calling model_descriptor_to_learner() on the provided ModelDescriptor that is received through the input channel. Then the parameters are set according to the parameters specified in PipeOpTorchModel and its '\$train() method is called on the [Task][mlr3::Task] stored

Super classes

```
mlr3pipelines::PipeOp -> mlr3pipelines::PipeOpLearner -> PipeOpTorchModel
```

Methods

Public methods:

- PipeOpTorchModel\$new()
- PipeOpTorchModel\$clone()

wise be set during construction.

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchModel$new(task_type, id = "torch_model", param_vals = list())
Arguments:
task_type (character(1))
   The task type of the model.
id (character(1))
   Identifier of the resulting object.
param_vals (list())
   List of hyperparameter settings, overwriting the hyperparameter settings that would other-
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

PipeOpTorchModel\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign, mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold, mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss, mlr_pipeops_torch_model_classif, mlr_pipeops_torch_model_regr

Description

Builds a torch classifier and trains it.

Parameters

See LearnerTorch

Input and Output Channels

There is one input channel "input" that takes in ModelDescriptor during training and a Task of the specified task_type during prediction. The output is NULL during training and a Prediction of given task_type during prediction.

State

A trained LearnerTorchModel.

Internals

A LearnerTorchModel is created by calling model_descriptor_to_learner() on the provided ModelDescriptor that is received through the input channel. Then the parameters are set according to the parameters specified in PipeOpTorchModel and its '\$train() method is called on the [Task][mlr3::Task] stored

Super classes

```
mlr3pipelines::PipeOp -> mlr3pipelines::PipeOpLearner -> mlr3torch::PipeOpTorchModel
-> PipeOpTorchModelClassif
```

Methods

Public methods:

- PipeOpTorchModelClassif\$new()
- PipeOpTorchModelClassif\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
PipeOpTorchModelClassif$new(id = "torch_model_classif", param_vals = list())
```

Arguments:

```
id (character(1))
```

Identifier of the resulting object.

```
param_vals (list())
```

List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
```

PipeOpTorchModelClassif\$clone(deep = FALSE)

Arguments:

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d, mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d, mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d, mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d, mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten, mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid, mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu, mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod, mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6, mlr_pipeops_nn_reshape, mlr_pipeops_nn_relu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid, mlr_pipeops_nn_softmax, mlr_pipeops_nn_softsign,
```

```
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_regr
```

Examples

```
# simple logistic regression

# configure the model descriptor
md = as_graph(po("torch_ingress_num") %>>%
    po("nn_head") %>>%
    po("torch_loss", "cross_entropy") %>>%
    po("torch_optimizer", "adam"))$train(tsk("iris"))[[1L]]

print(md)

# build the learner from the model descriptor and train it
po_model = po("torch_model_classif", batch_size = 50, epochs = 1)
po_model$train(list(md))
po_model$state
```

```
mlr_pipeops_torch_model_regr

Torch Regression Model
```

Description

Builds a torch regression model and trains it.

Parameters

See LearnerTorch

Input and Output Channels

There is one input channel "input" that takes in ModelDescriptor during training and a Task of the specified task_type during prediction. The output is NULL during training and a Prediction of given task_type during prediction.

State

A trained LearnerTorchModel.

Internals

A LearnerTorchModel is created by calling model_descriptor_to_learner() on the provided ModelDescriptor that is received through the input channel. Then the parameters are set according to the parameters specified in PipeOpTorchModel and its '\$train() method is called on the [Task][mlr3::Task] stored

Super classes

```
mlr3pipelines::PipeOp -> mlr3pipelines::PipeOpLearner -> mlr3torch::PipeOpTorchModel
-> PipeOpTorchModelRegr
```

Methods

Public methods:

- PipeOpTorchModelRegr\$new()
- PipeOpTorchModelRegr\$clone()

```
Method new(): Creates a new instance of this R6 class.
```

```
Usage:
PipeOpTorchModelRegr$new(id = "torch_model_regr", param_vals = list())
Arguments:
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchModelRegr$clone(deep = FALSE)
Arguments:
```

deep Whether to make a deep clone.

See Also

```
Other PipeOps: mlr_pipeops_nn_avg_pool1d, mlr_pipeops_nn_avg_pool2d, mlr_pipeops_nn_avg_pool3d,
mlr_pipeops_nn_batch_norm1d, mlr_pipeops_nn_batch_norm2d, mlr_pipeops_nn_batch_norm3d,
mlr_pipeops_nn_block, mlr_pipeops_nn_celu, mlr_pipeops_nn_conv1d, mlr_pipeops_nn_conv2d,
mlr_pipeops_nn_conv3d, mlr_pipeops_nn_conv_transpose1d, mlr_pipeops_nn_conv_transpose2d,
mlr_pipeops_nn_conv_transpose3d, mlr_pipeops_nn_dropout, mlr_pipeops_nn_elu, mlr_pipeops_nn_flatten,
mlr_pipeops_nn_gelu, mlr_pipeops_nn_glu, mlr_pipeops_nn_hardshrink, mlr_pipeops_nn_hardsigmoid,
mlr_pipeops_nn_hardtanh, mlr_pipeops_nn_head, mlr_pipeops_nn_layer_norm, mlr_pipeops_nn_leaky_relu,
mlr_pipeops_nn_linear, mlr_pipeops_nn_log_sigmoid, mlr_pipeops_nn_max_pool1d, mlr_pipeops_nn_max_pool2d
mlr_pipeops_nn_max_pool3d, mlr_pipeops_nn_merge, mlr_pipeops_nn_merge_cat, mlr_pipeops_nn_merge_prod,
mlr_pipeops_nn_merge_sum, mlr_pipeops_nn_prelu, mlr_pipeops_nn_relu, mlr_pipeops_nn_relu6,
mlr_pipeops_nn_reshape, mlr_pipeops_nn_rrelu, mlr_pipeops_nn_selu, mlr_pipeops_nn_sigmoid,
mlr_pipeops_nn_softmax, mlr_pipeops_nn_softplus, mlr_pipeops_nn_softshrink, mlr_pipeops_nn_softsign,
mlr_pipeops_nn_squeeze, mlr_pipeops_nn_tanh, mlr_pipeops_nn_tanhshrink, mlr_pipeops_nn_threshold,
mlr_pipeops_nn_unsqueeze, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ,
mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, mlr_pipeops_torch_loss,
mlr_pipeops_torch_model, mlr_pipeops_torch_model_classif
```

Examples

```
# simple linear regression

# build the model descriptor

md = as_graph(po("torch_ingress_num") %>>%
    po("nn_head") %>>%
    po("torch_loss", "mse") %>>%
    po("torch_optimizer", "adam"))$train(tsk("mtcars"))[[1L]]

print(md)

# build the learner from the model descriptor and train it
po_model = po("torch_model_regr", batch_size = 20, epochs = 1)
po_model$train(list(md))
po_model$state
```

```
mlr_pipeops_torch_optimizer

Optimizer Configuration
```

Description

Configures the optimizer of a deep learning model.

Input and Output Channels

There is one input channel "input" and one output channel "output". During *training*, the channels are of class ModelDescriptor. During *prediction*, the channels are of class Task.

State

The state is the value calculated by the public method shapes_out().

Parameters

The parameters are defined dynamically from the optimizer that is set during construction.

Internals

During training, the optimizer is cloned and added to the ModelDescriptor. Note that the parameter set of the stored TorchOptimizer is reference-identical to the parameter set of the pipeop itself.

Super class

```
mlr3pipelines::PipeOp -> PipeOpTorchOptimizer
```

Methods

Public methods:

- PipeOpTorchOptimizer\$new()
- PipeOpTorchOptimizer\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
PipeOpTorchOptimizer$new(
    optimizer = t_opt("adam"),
    id = "torch_optimizer",
    param_vals = list()
)

Arguments:
optimizer (TorchOptimizer or character(1) or torch_optimizer_generator)
    The optimizer (or something convertible via as_torch_optimizer()).
id (character(1))
    Identifier of the resulting object.
param_vals (list())
    List of hyperparameter settings, overwriting the hyperparameter settings that would otherwise be set during construction.
```

Method clone(): The objects of this class are cloneable with this method.

```
Usage:
PipeOpTorchOptimizer$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other PipeOp: mlr_pipeops_module, mlr_pipeops_torch_callbacks
Other Model Configuration: ModelDescriptor(), mlr_pipeops_torch_callbacks, mlr_pipeops_torch_loss, model_descriptor_union()
```

Examples

```
po_opt = po("torch_optimizer", "sgd", lr = 0.01)
po_opt$param_set
mdin = po("torch_ingress_num")$train(list(tsk("iris")))
mdin[[1L]]$optimizer
mdout = po_opt$train(mdin)
mdout[[1L]]$optimizer
```

Description

Calls torchvision::transform_adjust_brightness, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
brightness_factor	numeric	-		$[0,\infty)$
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
{\it mlr\_pipeops\_trafo\_adjust\_gamma} \\ {\it PipeOpPreprocTorchTrafoAdjustGamma}
```

Description

Calls torchvision::transform_adjust_gamma, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id Type Default Levels I	Range
gamma numeric -	$[0,\infty)$
gain numeric 1	$(-\infty, \infty)$
stages character - train, predict, both -	-
affect_columns untyped selector_all() -	-

```
mlr_pipeops_trafo_adjust_hue
```

Pipe Op Preproc Torch Trafo Adjust Hue

Description

Calls torchvision::transform_adjust_hue, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
hue_factor	numeric	-		[-0.5, 0.5]
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
{\tt mlr\_pipeops\_trafo\_adjust\_saturation}
```

Pipe Op Preproc Torch Trafo Adjust Saturation

Description

Calls torchvision::transform_adjust_saturation, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
saturation_factor	numeric	-		$(-\infty,\infty)$
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
\label{linear_pipe} \verb|mlr_pipeops_trafo_grayscale| \\ PipeOpPreprocTorchTrafoGrayscale|
```

Description

Calls torchvision::transform_grayscale, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels	Range
num_output_channels	integer	-		[1, 3]
stages	character	-	train, predict, both	-
affect_columns	untyped	selector_all()		-

```
mlr_pipeops_trafo_nop PipeOpPreprocTorchTrafoNop
```

Description

Does nothing.

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

```
mlr_pipeops_trafo_normalize
```

Pipe Op Preproc Torch Trafo Normalize

Description

Calls torchvision::transform_normalize, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
mean	untyped	-	
std	untyped	-	
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

```
mlr\_pipeops\_trafo\_pad PipeOpPreprocTorchTrafoPad
```

Description

Calls torchvision::transform_pad, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
padding	untyped	-	
fill	untyped	0	
padding_mode	character	constant	constant, edge, reflect, symmetric
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

mlr_pipeops_trafo_reshape

PipeOpPreprocTorchTrafoReshape

Description

Reshapes the tensor according to the parameter shape, by calling torch_reshape(). This preprocessing function is applied batch-wise.

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

shape :: integer()
 The desired output shape. The first dimension is the batch dimension and should usually be
-1.

mlr_pipeops_trafo_resize

PipeOpPreprocTorchTrafoResize

Description

Calls torchvision::transform_resize, see there for more information on the parameters. The preprocessing is applied to the whole batch.

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

Id	Type	Default	Levels
size	untyped	-	
interpolation	character	2	Undefined, Bartlett, Blackman, Bohman, Box, Catrom, Cosine, Cubic, Gaussian
stages	character	-	train, predict, both
affect_columns	untyped	selector_all()	

198 mlr_tasks_lazy_iris

Description

Calls torchvision::transform_rgb_to_grayscale, see there for more information on the parameters. The preprocessing is applied row wise (no batch dimension).

Format

R6Class inheriting from PipeOpTaskPreprocTorch.

Parameters

```
IdTypeDefaultLevelsstagescharacter-train, predict, bothaffect_columnsuntypedselector_all()
```

Description

A classification task for the popular datasets::iris data set. Just like the iris task, but the features are represented as one lazy tensor column.

Format

R6::R6Class inheriting from mlr3::TaskClassif.

Construction

```
tsk("lazy_iris")
```

Properties

Task type: "classif" Properties: "multiclass"

Has Missings: no Target: "Species"

• Features: "x"

• Data Dimension: 150x3

mlr_tasks_mnist

Source

```
https://en.wikipedia.org/wiki/Iris_flower_data_set
```

References

Anderson E (1936). "The Species Problem in Iris." *Annals of the Missouri Botanical Garden*, **23**(3), 457. doi:10.2307/2394164.

Examples

```
task = tsk("lazy_iris")
task
df = task$data()
materialize(df$x[1:6], rbind = TRUE)
```

mlr_tasks_mnist

MNIST Image classification

Description

Classic MNIST image classification.

The underlying DataBackend contains columns "label", "image", "row_id", "split", where the last column indicates whether the row belongs to the train or test set.

The first 60000 rows belong to the training set, the last 10000 rows to the test set.

Construction

```
tsk("mnist")
```

Download

The task's backend is a DataBackendLazy which will download the data once it is requested. Other meta-data is already available before that. You can cache these datasets by setting the mlr3torch.cache option to TRUE or to a specific path to be used as the cache directory.

Properties

• Task type: "classif"

• Properties: "multiclass"

· Has Missings: no

• Target: "label"

• Features: "image"

• Data Dimension: 70000x4

Source

https://torchvision.mlverse.org/reference/mnist_dataset.html

References

Lecun, Y., Bottou, L., Bengio, Y., Haffner, P. (1998). "Gradient-based learning applied to document recognition." *Proceedings of the IEEE*, **86**(11), 2278-2324. doi:10.1109/5.726791.

Examples

```
task = tsk("mnist")
task
```

```
mlr_tasks_tiny_imagenet
```

Tiny ImageNet Classification Task

Description

Subset of the famous ImageNet dataset. The data is obtained from torchvision::tiny_imagenet_dataset().

The underlying DataBackend contains columns "class", "image", "..row_id", "split", where the last column indicates whether the row belongs to the train, validation or test set that defined provided in torchvision.

There are no labels for the test rows, so by default, these observations are inactive, which means that the task uses only 110000 of the 120000 observations that are defined in the underlying data backend.

Construction

```
tsk("tiny_imagenet")
```

Download

The task's backend is a DataBackendLazy which will download the data once it is requested. Other meta-data is already available before that. You can cache these datasets by setting the mlr3torch.cache option to TRUE or to a specific path to be used as the cache directory.

Properties

• Task type: "classif"

• Properties: "multiclass"

Has Missings: no

• Target: "class"

· Features: "image"

• Data Dimension: 120000x4

ModelDescriptor 201

References

Deng, Jia, Dong, Wei, Socher, Richard, Li, Li-Jia, Li, Kai, Fei-Fei, Li (2009). "Imagenet: A large-scale hierarchical image database." In 2009 IEEE conference on computer vision and pattern recognition, 248–255. IEEE.

Examples

```
task = tsk("tiny_imagenet")
task
```

ModelDescriptor

Represent a Model with Meta-Info

Description

Represents a *model*; possibly a complete model, possibly one in the process of being built up.

This model takes input tensors of shapes shapes_in and pipes them through graph. Input shapes get mapped to input channels of graph. Output shapes are named by the output channels of graph; it is also possible to represent no-ops on tensors, in which case names of input and output should be identical.

ModelDescriptor objects typically represent partial models being built up, in which case the pointer slot indicates a specific point in the graph that produces a tensor of shape pointer_shape, on which the graph should be extended. It is allowed for the graph in this structure to be modified by-reference in different parts of the code. However, these modifications may never add edges with elements of the Graph as destination. In particular, no element of graph\$input may be removed by reference, e.g. by adding an edge to the Graph that has the input channel of a PipeOp that was previously without parent as its destination.

In most cases it is better to create a specific ModelDescriptor by training a Graph consisting (mostly) of operators PipeOpTorchIngress, PipeOpTorch, PipeOpTorchLoss, PipeOpTorchOptimizer, and PipeOpTorchCallbacks.

A ModelDescriptor can be converted to a nn_graph via model_descriptor_to_module.

Usage

```
ModelDescriptor(
  graph,
  ingress,
  task,
  optimizer = NULL,
  loss = NULL,
  callbacks = NULL,
  pointer = NULL,
  pointer_shape = NULL
)
```

Arguments

graph (Graph)

Graph of PipeOpModule and PipeOpNOP operators.

ingress (uniquely named list of TorchIngressToken)

List of inputs that go into graph. Names of this must be a subset of graph\$input\$name.

task (Task)

(Training)-Task for which the model is being built. May be necessary for for

some aspects of what loss to use etc.

optimizer (TorchOptimizer | NULL)

Additional info: what optimizer to use.

loss (TorchLoss | NULL)

Additional info: what loss to use.

callbacks (A list of CallbackSet or NULL)

Additional info: what callbacks to use.

pointer (character(2) | NULL)

Indicating an element on which a model is. Points to an output channel within graph: Element 1 is the PipeOp's id and element 2 is that PipeOp's output

channel.

pointer_shape (integer | NULL)

Shape of the output indicated by pointer.

Value

(ModelDescriptor)

See Also

Other Model Configuration: mlr_pipeops_torch_callbacks, mlr_pipeops_torch_loss, mlr_pipeops_torch_optimize model_descriptor_union()

Other Graph Network: TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()

model_descriptor_to_learner

Create a Torch Learner from a ModelDescriptor

Description

First a nn_graph is created using model_descriptor_to_module and then a learner is created from this module and the remaining information from the model descriptor, which must include the optimizer and loss function and optionally callbacks.

Usage

```
model_descriptor_to_learner(model_descriptor)
```

Arguments

Value

Learner

See Also

Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, model_descriptor_to_module(), model_descriptor_union(), nn_graph()

Description

Creates the nn_graph from a ModelDescriptor. Mostly for internal use, since the ModelDescriptor is in most circumstances harder to use than just creating nn_graph directly.

Usage

```
model_descriptor_to_module(
  model_descriptor,
  output_pointers = NULL,
  list_output = FALSE
)
```

Arguments

```
model_descriptor

(ModelDescriptor)

Model Descriptor. pointer is ignored, instead output_pointer values are used. $graph member is modified by-reference.

output_pointers

(list of character)

Collection of pointers that indicate what part of the model_descriptor$graph is being used for output. Entries have the format of ModelDescriptor$pointer.
```

```
list_output (logical(1))
```

Whether output should be a list of tensors. If FALSE, then length(output_pointers) must be 1.

Value

```
nn_graph
```

See Also

Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_union(), nn_graph()

```
model_descriptor_union
```

Union of ModelDescriptors

Description

This is a mostly internal function that is used in PipeOpTorchs with multiple input channels.

It creates the union of multiple ModelDescriptors:

- graphs are combinded (if they are not identical to begin with). The first entry's graph is modified by reference.
- PipeOps with the same ID must be identical. No new input edges may be added to PipeOps.
- Drops pointer / pointer_shape entries.
- The new task is the feature union of the two incoming tasks.
- The optimizer and loss of both ModelDescriptors must be identical.
- Ingress tokens and callbacks are merged, where objects with the same "id" must be identical.

Usage

```
model_descriptor_union(md1, md2)
```

Arguments

```
md1 (ModelDescriptor) The first ModelDescriptor.
md2 (ModelDescriptor) The second ModelDescriptor.
```

Details

The requirement that no new input edgedes may be added to PipeOps is not theoretically necessary, but since we assume that ModelDescriptor is being built from beginning to end (i.e. PipeOps never get new ancestors) we can make this assumption and simplify things. Otherwise we'd need to treat "..."-inputs special.)

nn 205

Value

ModelDescriptor

See Also

```
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), nn_graph()
```

 $Other\ Model\ Configuration:\ Model\ Descriptor(), \ mlr_pipeops_torch_callbacks, \ mlr_pipeops_torch_loss, \ mlr_pipeops_torch_optimizer$

nn

Create a Neural Network Layer

Description

Retrieve a neural network layer from the mlr_pipeops dictionary.

Usage

```
nn(.key, ...)
```

Arguments

```
.key (character(1))... (any)Additional parameters, constructor arguments or fields.
```

Examples

```
po1 = po("nn_linear", id = "linear")
# is the same as:
po2 = nn("linear")
```

206 nn_graph

nn_graph	Graph Network		
----------	---------------	--	--

Description

Represents a neural network using a Graph that usually costains mostly PipeOpModules.

Usage

```
nn_graph(graph, shapes_in, output_map = graph$output$name, list_output = FALSE)
```

Arguments

graph (Graph)

The Graph to wrap. Is **not** cloned.

shapes_in (named integer)

Shape info of tensors that go into graph. Names must be graph\$input\$name,

possibly in different order.

output_map (character)

Which of graph's outputs to use. Must be a subset of graph\$output\$name.

list_output (logical(1))

Whether output should be a list of tensors. If FALSE (default), then length(output_map)

must be 1.

Value

```
nn_graph
```

See Also

```
Other Graph Network: ModelDescriptor(), TorchIngressToken(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_ltnsr, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union()
```

Examples

```
graph = mlr3pipelines::Graph$new()
graph$add_pipeop(po("module_1", module = nn_linear(10, 20)), clone = FALSE)
graph$add_pipeop(po("module_2", module = nn_relu()), clone = FALSE)
graph$add_pipeop(po("module_3", module = nn_linear(20, 1)), clone = FALSE)
graph$add_edge("module_1", "module_2")
graph$add_edge("module_2", "module_3")
network = nn_graph(graph, shapes_in = list(module_1.input = c(NA, 10)))
x = torch_randn(16, 10)
```

nn_merge_cat 207

```
network(module_1.input = x)
```

 nn_merge_cat

Concatenates multiple tensors

Description

Concatenates multiple tensors on a given dimension. No broadcasting rules are applied here, you must reshape the tensors before to have the same shape.

Usage

```
nn_merge_cat(dim = -1)
```

Arguments

dim

(integer(1))

The dimension for the concatenation.

nn_merge_prod

Product of multiple tensors

Description

Calculates the product of all input tensors.

Usage

```
nn_merge_prod()
```

nn_merge_sum

Sum of multiple tensors

Description

Calculates the sum of all input tensors.

Usage

```
nn_merge_sum()
```

208 nn_unsqueeze

nn_reshape

Reshape

Description

Reshape a tensor to the given shape.

Usage

```
nn_reshape(shape)
```

Arguments

shape

(integer())

The desired output shape.

nn_squeeze

Squeeze

Description

Squeezes a tensor by calling torch::torch_squeeze() with the given dimension dim.

Usage

```
nn_squeeze(dim)
```

Arguments

dim

(integer())

The dimension to squeeze.

nn_unsqueeze

Unsqueeze

Description

Unsqueezes a tensor by calling torch::torch_unsqueeze() with the given dimension dim.

Usage

```
nn_unsqueeze(dim)
```

Arguments

dim

(integer(1))

The dimension to unsqueeze.

Description

Function to create objects of class PipeOpTaskPreprocTorch in a more convenient way. Start by reading the documentation of PipeOpTaskPreprocTorch.

Usage

```
pipeop_preproc_torch(
   id,
   fn,
   shapes_out = NULL,
   param_set = NULL,
   packages = character(0),
   rowwise = FALSE,
   parent_env = parent.frame(),
   stages_init = NULL,
   tags = NULL
)
```

Arguments

id (character(1))

The id for of the new object.

fn (function)

The preprocessing function.

shapes_out (function or NULL or "infer")

The private .shapes_out(shapes_in, param_vals, task) method of PipeOpTaskPreprocTorch (see section Inheriting). Special values are NULL and infer: If NULL, the output shapes are unknown. If "infer", the output shape function is inferred and calculates the output shapes as follows: For an input shape of (NA, ...) a meta-tensor of shape (1, ...) is created and the preprocessing function is applied. Afterwards the batch dimension (1) is replaced with NA and the shape is returned. If the

first dimension is not NA, the output shape of applying the preprocessing function is returned. Method "infer" should be correct in most cases, but might fail in some edge cases.

m some eage eases.

param_set (ParamSet or NULL)

The parameter set. If this is left as NULL (default) the parameter set is inferred in the following way: All parameters but the first and . . . of fn are set as untyped parameters with tags 'train' and those that have no default value are tagged as

'required' as well. Default values are not annotated.

packages (character())

The R packages this object depends on.

210 task_dataset

rowwise (logical(1))

Whether the preprocessing is applied row-wise.

parent_env (environment)

The parent environment for the R6 class.

stages_init (character(1))

Initial value for the stages parameter. If NULL (default), will be set to "both" in case the id starts with "trafo" and to "train" if it starts with "augment".

Otherwise it must specified.

tags (character())

Tags for the pipeop

Value

An R6Class instance inheriting from PipeOpTaskPreprocTorch

Examples

```
\label{eq:pipeOpPreprocExample = pipeop_preproc_torch("preproc_example", function(x, a) x + a) \\ po_example = PipeOpPreprocExample$new() \\ po_example$param_set
```

task_dataset

Create a Dataset from a Task

Description

Creates a torch dataset from an mlr3 Task. The resulting dataset's \$.get_batch() method returns a list with elements x, y and index:

- x is a list with tensors, whose content is defined by the parameter feature_ingress_tokens.
- y is the target variable and its content is defined by the parameter target_batchgetter.
- . index is the index of the batch in the task's data.

The data is returned on the device specified by the parameter device.

Usage

```
task_dataset(task, feature_ingress_tokens, target_batchgetter = NULL, device)
```

Arguments

task (Task)

The task for which to build the dataset.

feature_ingress_tokens

(named list() of TorchIngressToken)

Each ingress token defines one item in the \$x value of a batch with corresponding names.

TorchCallback 211

Value

torch::dataset

Examples

```
task = tsk("iris")
sepal_ingress = TorchIngressToken(
 features = c("Sepal.Length", "Sepal.Width"),
 batchgetter = batchgetter_num,
 shape = c(NA, 2)
petal_ingress = TorchIngressToken(
 features = c("Petal.Length", "Petal.Width"),
 batchgetter = batchgetter_num,
 shape = c(NA, 2)
)
ingress_tokens = list(sepal = sepal_ingress, petal = petal_ingress)
target_batchgetter = function(data, device) {
 torch_tensor(data = data[[1L]], dtype = torch_float32(), device)$unsqueeze(2)
dataset = task_dataset(task, ingress_tokens, target_batchgetter, "cpu")
batch = dataset$.getbatch(1:10)
batch
```

TorchCallback

Torch Callback

Description

This wraps a CallbackSet and annotates it with metadata, most importantly a ParamSet. The callback is created for the given parameter values by calling the \$generate() method.

This class is usually used to configure the callback of a torch learner, e.g. when constructing a learner of in a ModelDescriptor.

For a list of available callbacks, see mlr3torch_callbacks. To conveniently retrieve a TorchCallback, use t_clbk().

212 **TorchCallback**

Parameters

Defined by the constructor argument param_set. If no parameter set is provided during construction, the parameter set is constructed by creating a parameter for each argument of the wrapped loss function, where the parametes are then of type ParamUty.

Super class

```
mlr3torch::TorchDescriptor->TorchCallback
```

Methods

Public methods:

```
TorchCallback$new()
```

• TorchCallback\$clone()

Method new(): Creates a new instance of this R6 class.

```
TorchCallback$new(
  callback_generator,
  param_set = NULL,
  id = NULL,
  label = NULL,
  packages = NULL,
  man = NULL
)
Arguments:
callback_generator (R6ClassGenerator)
   The class generator for the callback that is being wrapped.
param_set (ParamSet or NULL)
   The parameter set. If NULL (default) it is inferred from callback_generator.
id (character(1))
   The id for of the new object.
label (character(1))
   Label for the new instance.
packages (character())
   The R packages this object depends on.
man (character(1))
   String in the format [pkg]::[topic] pointing to a manual page for this object. The refer-
   enced help package can be opened via method $help().
```

Method clone(): The objects of this class are cloneable with this method.

```
TorchCallback$clone(deep = FALSE)
Arguments:
deep Whether to make a deep clone.
```

TorchDescriptor 213

See Also

```
Other Callback: as_torch_callback(), as_torch_callbacks(), callback_set(), mlr3torch_callbacks, mlr_callback_set, mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch, t_clbk(), torch_callback()

Other Torch Descriptor: TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(), t_loss(), t_opt()
```

Examples

```
# Create a new torch callback from an existing callback set
torch_callback = TorchCallback$new(CallbackSetCheckpoint)
# The parameters are inferred
torch_callback$param_set
# Retrieve a torch callback from the dictionary
torch_callback = t_clbk("checkpoint",
  path = tempfile(), freq = 1
)
torch_callback
torch_callback$label
torch_callback$id
# open the help page of the wrapped callback set
# torch_callback$help()
# Create the callback set
callback = torch_callback$generate()
callback
# is the same as
CallbackSetCheckpoint$new(
  path = tempfile(), freq = 1
)
# Use in a learner
learner = lrn("regr.mlp", callbacks = t_clbk("checkpoint"))
# the parameters of the callback are added to the learner's parameter set
learner$param_set
```

TorchDescriptor

Base Class for Torch Descriptors

Description

Abstract Base Class from which TorchLoss, TorchOptimizer, and TorchCallback inherit. This class wraps a generator (R6Class Generator or the torch version of such a generator) and annotates it with metadata such as a ParamSet, a label, an ID, packages, or a manual page.

The parameters are the construction arguments of the wrapped generator and the parameter \$values are passed to the generator when calling the public method \$generate().

214 TorchDescriptor

Parameters

Defined by the constructor argument param_set. All parameters are tagged with "train", but this is done automatically during initialize.

Public fields

```
label (character(1))
    Label for this object. Can be used in tables, plot and text output instead of the ID.
param_set (ParamSet)
    Set of hyperparameters.
packages (character(1))
    Set of required packages. These packages are loaded, but not attached.
id (character(1))
    Identifier of the object. Used in tables, plot and text output.
generator The wrapped generator that is described.
man (character(1))
    String in the format [pkg]::[topic] pointing to a manual page for this object.
```

Active bindings

```
phash (character(1))
```

Hash (unique identifier) for this partial object, excluding some components which are varied systematically (e.g. the parameter values).

Methods

Public methods:

- TorchDescriptor\$new()
- TorchDescriptor\$print()
- TorchDescriptor\$generate()
- TorchDescriptor\$help()
- TorchDescriptor\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
```

```
TorchDescriptor$new(
    generator,
    id = NULL,
    param_set = NULL,
    packages = NULL,
    label = NULL,
    man = NULL)

Arguments:

generator The wrapped generator that is described.
```

TorchDescriptor 215

```
id (character(1))
           The id for of the new object.
       param_set (ParamSet)
           The parameter set.
       packages (character())
           The R packages this object depends on.
       label (character(1))
           Label for the new instance.
       man (character(1))
           String in the format [pkg]::[topic] pointing to a manual page for this object. The refer-
           enced help package can be opened via method $help().
     Method print(): Prints the object
       Usage:
       TorchDescriptor$print(...)
       Arguments:
       ... any
     Method generate(): Calls the generator with the given parameter values.
       Usage:
       TorchDescriptor$generate()
     Method help(): Displays the help file of the wrapped object.
       Usage:
       TorchDescriptor$help()
     Method clone(): The objects of this class are cloneable with this method.
       Usage:
       TorchDescriptor$clone(deep = FALSE)
       Arguments:
       deep Whether to make a deep clone.
See Also
    Other Torch Descriptor: TorchCallback, TorchLoss, TorchOptimizer, as_torch_callbacks(),
    as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(),
    t_loss(), t_opt()
```

216 TorchIngressToken

TorchIngressToken	Torch Ingress Token	
-------------------	---------------------	--

Description

This function creates an S3 class of class "TorchIngressToken", which is an internal data structure. It contains the (meta-)information of how a batch is generated from a Task and fed into an entry point of the neural network. It is stored as the ingress field in a ModelDescriptor.

Usage

TorchIngressToken(features, batchgetter, shape)

Arguments

features (character)

Features on which the batchgetter will operate.

batchgetter (function)

Function with two arguments: data and device. This function is given the output of Task\$data(rows = batch_indices, cols = features) and it should

produce a tensor of shape shape_out.

shape (integer)

Shape that batchgetter will produce. Batch-dimension should be included as

NA.

Value

TorchIngressToken object.

See Also

```
Other Graph Network: ModelDescriptor(), mlr_learners_torch_model, mlr_pipeops_module, mlr_pipeops_torch, mlr_pipeops_torch_ingress, mlr_pipeops_torch_ingress_categ, mlr_pipeops_torch_ingress_num, model_descriptor_to_learner(), model_descriptor_to_module(), model_descriptor_union(), nn_graph()
```

Examples

```
# Define a task for which we want to define an ingress token
task = tsk("iris")

# We create an ingress token for two feature Sepal.Length and Petal.Length:
# We have to specify the features, the batchgetter and the shape
features = c("Sepal.Length", "Petal.Length")
# As a batchgetter we use batchgetter_num

batch_dt = task$data(rows = 1:10, cols =features)
batch_dt
```

TorchLoss 217

```
batch_tensor = batchgetter_num(batch_dt, "cpu")
batch_tensor

# The shape is unknown in the first dimension (batch dimension)
ingress_token = TorchIngressToken(
  features = features,
  batchgetter = batchgetter_num,
  shape = c(NA, 2)
)
ingress_token
```

TorchLoss

Torch Loss

Description

This wraps a torch::nn_loss and annotates it with metadata, most importantly a ParamSet. The loss function is created for the given parameter values by calling the \$generate() method.

This class is usually used to configure the loss function of a torch learner, e.g. when construcing a learner or in a ModelDescriptor.

For a list of available losses, see mlr3torch_losses. Items from this dictionary can be retrieved using t_loss().

Parameters

Defined by the constructor argument param_set. If no parameter set is provided during construction, the parameter set is constructed by creating a parameter for each argument of the wrapped loss function, where the parametes are then of type ParamUty.

Super class

```
mlr3torch::TorchDescriptor -> TorchLoss
```

Public fields

```
task_types (character())
    The task types this loss supports.
```

Methods

Public methods:

- TorchLoss\$new()
- TorchLoss\$print()
- TorchLoss\$clone()

Method new(): Creates a new instance of this R6 class.

218 TorchLoss

```
Usage:
       TorchLoss$new(
         torch_loss,
         task_types = NULL,
         param_set = NULL,
         id = NULL,
         label = NULL,
         packages = NULL,
         man = NULL
       )
       Arguments:
       torch_loss (nn_loss)
           The loss module.
       task_types (character())
           The task types supported by this loss.
       param_set (ParamSet or NULL)
           The parameter set. If NULL (default) it is inferred from torch_loss.
       id (character(1))
           The id for of the new object.
       label (character(1))
           Label for the new instance.
       packages (character())
           The R packages this object depends on.
       man (character(1))
           String in the format [pkg]::[topic] pointing to a manual page for this object. The refer-
           enced help package can be opened via method $help().
     Method print(): Prints the object
       Usage:
       TorchLoss$print(...)
       Arguments:
       ... any
     Method clone(): The objects of this class are cloneable with this method.
       Usage:
       TorchLoss$clone(deep = FALSE)
       Arguments:
       deep Whether to make a deep clone.
See Also
    Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchOptimizer, as_torch_callbacks(),
    as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(),
```

t_loss(), t_opt()

TorchOptimizer 219

Examples

```
# Create a new torch loss
torch_loss = TorchLoss$new(torch_loss = nn_mse_loss, task_types = "regr")
torch_loss
# the parameters are inferred
torch_loss$param_set
# Retrieve a loss from the dictionary:
torch_loss = t_loss("mse", reduction = "mean")
# is the same as
torch_loss
torch_loss$param_set
torch_loss$label
torch_loss$task_types
torch_loss$id
# Create the loss function
loss_fn = torch_loss$generate()
loss_fn
# Is the same as
nn_mse_loss(reduction = "mean")
# open the help page of the wrapped loss function
# torch_loss$help()
# Use in a learner
learner = lrn("regr.mlp", loss = t_loss("mse"))
# The parameters of the loss are added to the learner's parameter set
learner$param_set
```

TorchOptimizer

Torch Optimizer

Description

This wraps a torch::torch_optimizer_generatora and annotates it with metadata, most importantly a ParamSet. The optimizer is created for the given parameter values by calling the \$generate() method.

This class is usually used to configure the optimizer of a torch learner, e.g. when construcing a learner or in a ModelDescriptor.

For a list of available optimizers, see $mlr3torch_optimizers$. Items from this dictionary can be retrieved using $t_opt()$.

Parameters

Defined by the constructor argument param_set. If no parameter set is provided during construction, the parameter set is constructed by creating a parameter for each argument of the wrapped loss function, where the parametes are then of type ParamUty.

220 TorchOptimizer

Super class

```
mlr3torch::TorchDescriptor -> TorchOptimizer
```

Methods

```
Public methods:
```

- TorchOptimizer\$new()
- TorchOptimizer\$generate()
- TorchOptimizer\$clone()

Method new(): Creates a new instance of this R6 class.

```
Usage:
TorchOptimizer$new(
  torch_optimizer,
  param_set = NULL,
  id = NULL,
  label = NULL,
  packages = NULL,
  man = NULL
)
Arguments:
torch_optimizer (torch_optimizer_generator)
   The torch optimizer.
param_set (ParamSet or NULL)
   The parameter set. If NULL (default) it is inferred from torch_optimizer.
id (character(1))
   The id for of the new object.
label (character(1))
   Label for the new instance.
packages (character())
   The R packages this object depends on.
man (character(1))
   String in the format [pkg]::[topic] pointing to a manual page for this object. The refer-
   enced help package can be opened via method $help().
```

Method generate(): Instantiates the optimizer.

```
Usage:
TorchOptimizer$generate(params)
Arguments:
params (named list() of torch_tensors)
   The parameters of the network.
Returns: torch_optimizer
```

Method clone(): The objects of this class are cloneable with this method.

Usage:

torch_callback 221

```
TorchOptimizer$clone(deep = FALSE)

Arguments:
deep Whether to make a deep clone.
```

See Also

```
Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, as_torch_callbacks(), as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(), t_loss(), t_opt()
```

Examples

```
# Create a new torch loss
torch_opt = TorchOptimizer$new(optim_adam, label = "adam")
torch opt
# If the param set is not specified, parameters are inferred but are of class ParamUty
torch_opt$param_set
# open the help page of the wrapped optimizer
# torch_opt$help()
# Retrieve an optimizer from the dictionary
torch_opt = t_opt("sgd", lr = 0.1)
torch_opt
torch_opt$param_set
torch_opt$label
torch_opt$id
# Create the optimizer for a network
net = nn_linear(10, 1)
opt = torch_opt$generate(net$parameters)
# is the same as
optim_sgd(net$parameters, lr = 0.1)
# Use in a learner
learner = lrn("regr.mlp", optimizer = t_opt("sgd"))
# The parameters of the optimizer are added to the learner's parameter set
learner$param_set
```

torch_callback

Create a Callback Desctiptor

Description

Convenience function to create a custom TorchCallback. All arguments that are available in callback_set() are also available here. For more information on how to correctly implement a new callback, see CallbackSet.

222 torch_callback

Usage

```
torch_callback(
  id,
  classname = paste0("CallbackSet", capitalize(id)),
  param_set = NULL,
  packages = NULL,
  label = capitalize(id),
 man = NULL,
 on_begin = NULL,
 on_end = NULL,
 on_exit = NULL,
 on_epoch_begin = NULL,
 on_before_valid = NULL,
  on_epoch_end = NULL,
  on_batch_begin = NULL,
  on_batch_end = NULL,
  on_after_backward = NULL,
  on_batch_valid_begin = NULL,
  on_batch_valid_end = NULL,
  on_valid_end = NULL,
  state_dict = NULL,
  load_state_dict = NULL,
  initialize = NULL,
  public = NULL,
  private = NULL,
  active = NULL,
 parent_env = parent.frame(),
  inherit = CallbackSet,
  lock_objects = FALSE
)
```

Arguments

```
id
                  (character(1))
                  The id for the torch callback.
classname
                  (character(1))
                  The class name.
                  (ParamSet)
param_set
                  The parameter set, if not present it is inferred from the $initialize() method.
packages
                  (character())
                  The packages the callback depends on. Default is NULL'.
label
                  (character(1))
                  The label for the torch callback. Defaults to the capitalized id.
man
                  (character(1))
                  String in the format [pkg]::[topic] pointing to a manual page for this object.
```

torch_callback 223

The referenced help package can be opened via method \$help(). The default is

NULL.

on_begin, on_end, on_epoch_begin, on_before_valid, on_epoch_end, on_batch_begin, on_batch_end, on_after_backward,

on_batch_valid_begin, on_batch_valid_end, on_valid_end, on_exit

(function)

Function to execute at the given stage, see section *Stages*.

state_dict (function())

The function that retrieves the state dict from the callback. This is what will be

available in the learner after training.

load_state_dict

(function(state_dict))

Function that loads a callback state.

initialize (function())

The initialization method of the callback.

public, private, active

(list())

Additional public, private, and active fields to add to the callback.

parent_env (environment())

The parent environment for the R6Class.

inherit (R6ClassGenerator)

From which class to inherit. This class must either be CallbackSet (default) or

inherit from it.

lock_objects (logical(1))

Whether to lock the objects of the resulting R6Class. If FALSE (default), values can be freely assigned to self without declaring them in the class definition.

Value

TorchCallback

Internals

It first creates an R6 class inheriting from CallbackSet (using callback_set()) and then wraps this generator in a TorchCallback that can be passed to a torch learner.

Stages

- begin :: Run before the training loop begins.
- epoch_begin :: Run he beginning of each epoch.
- batch_begin :: Run before the forward call.
- after_backward :: Run after the backward call.
- batch_end :: Run after the optimizer step.
- batch_valid_begin :: Run before the forward call in the validation loop.
- batch_valid_end :: Run after the forward call in the validation loop.

224 t_clbk

- valid_end :: Run at the end of validation.
- epoch_end :: Run at the end of each epoch.
- end :: Run after last epoch.
- exit :: Run at last, using on.exit().

See Also

```
Other \ Callback: \ Torch Callback, as\_torch\_callback(), as\_torch\_callbacks(), callback\_set(), \\ mlr3torch\_callbacks, mlr\_callback\_set, mlr\_callback\_set.checkpoint, mlr\_callback\_set.progress, \\ mlr\_context\_torch, t\_clbk()
```

Examples

```
custom_tcb = torch_callback("custom",
  initialize = function(name) {
   self$name = name
  },
  on_begin = function() {
   cat("Hello", self$name, ", we will train for ", self$ctx$total_epochs, "epochs.\n")
  },
  on_end = function() {
   cat("Training is done.")
)
learner = lrn("classif.torch_featureless",
  batch_size = 16,
  epochs = 1,
  callbacks = custom_tcb,
  cb.custom.name = "Marie",
  device = "cpu"
)
task = tsk("iris")
learner$train(task)
```

t_clbk

Sugar Function for Torch Callback

Description

Retrieves one or more TorchCallbacks from mlr3torch_callbacks. Works like mlr3::lrn() and mlr3::lrns().

Usage

```
t_clbk(.key, ...)
t_clbks(.keys)
```

t_loss 225

Arguments

Value

```
TorchCallback
```

list() of TorchCallbacks

See Also

```
Other Callback: TorchCallback, as_torch_callback(), as_torch_callbacks(), callback_set(), mlr3torch_callbacks, mlr_callback_set, mlr_callback_set.checkpoint, mlr_callback_set.progress, mlr_context_torch, torch_callback()

Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_loss(), t_opt()
```

Examples

```
t_clbk("progress")
```

t_loss

Loss Function Quick Access

Description

Retrieve one or more TorchLosses from mlr3torch_losses. Works like mlr3::lrn() and mlr3::lrns().

Usage

```
t_loss(.key, ...)
t_losses(.keys, ...)
```

Arguments

226 t_opt

Value

A TorchLoss

See Also

```
Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as\_torch\_callbacks(), as\_torch\_loss(), as\_torch\_optimizer(), mlr3torch\_losses, mlr3torch\_optimizers, t\_clbk(), t\_opt()\\
```

Examples

```
t_loss("mse", reduction = "mean")
# get the dictionary
t_loss()

t_losses(c("mse", "l1"))
# get the dictionary
t_losses()
```

t_opt

Optimizers Quick Access

Description

Retrieves one or more TorchOptimizers from mlr3torch_optimizers. Works like mlr3::lrn() and mlr3::lrns().

Usage

```
t_opt(.key, ...)
t_opts(.keys, ...)
```

Arguments

Value

A TorchOptimizer

t_opt 227

See Also

 $Other Torch Descriptor: TorchCallback, TorchDescriptor, TorchLoss, TorchOptimizer, as_torch_callbacks(), as_torch_loss(), as_torch_optimizer(), mlr3torch_losses, mlr3torch_optimizers, t_clbk(), t_loss()\\$

 $Other\ Dictionary: \verb|mlr3| torch_callbacks|, \verb|mlr3| torch_losses|, \verb|mlr3| torch_optimizers|$

Examples

```
t_opt("adam", lr = 0.1)
# get the dictionary
t_opt()

t_opts(c("adam", "sgd"))
# get the dictionary
t_opts()
```

Index

* Callback	mlr_learners_torch_model, 51
as_torch_callback, 9	* Model Configuration
as_torch_callbacks, 10	mlr_pipeops_torch_callbacks, 172
callback_set, 13	mlr_pipeops_torch_loss, 182
mlr3torch_callbacks, 20	mlr_pipeops_torch_optimizer, 191
mlr_callback_set, 25	<pre>model_descriptor_union, 204</pre>
mlr_callback_set.checkpoint,28	ModelDescriptor, 201
mlr_callback_set.progress, 30	* PipeOps
mlr_context_torch, 32	mlr_pipeops_nn_avg_pool1d,65
t_clbk, 224	mlr_pipeops_nn_avg_pool2d,67
torch_callback, 221	mlr_pipeops_nn_avg_pool3d,69
TorchCallback, 211	<pre>mlr_pipeops_nn_batch_norm1d, 71</pre>
* Dictionary	<pre>mlr_pipeops_nn_batch_norm2d, 73</pre>
mlr3torch_callbacks, 20	<pre>mlr_pipeops_nn_batch_norm3d, 75</pre>
mlr3torch_losses, 20	mlr_pipeops_nn_block,77
mlr3torch_optimizers, 21	mlr_pipeops_nn_celu,79
t_opt, 226	mlr_pipeops_nn_conv1d, 81
* Graph Network	mlr_pipeops_nn_conv2d,83
mlr_learners_torch_model, 51	mlr_pipeops_nn_conv3d, 85
mlr_pipeops_module, 62	mlr_pipeops_nn_conv_transpose1d
mlr_pipeops_torch, 166	87
mlr_pipeops_torch_ingress, 174	mlr_pipeops_nn_conv_transpose2d
<pre>mlr_pipeops_torch_ingress_categ,</pre>	90
176	mlr_pipeops_nn_conv_transpose3d
<pre>mlr_pipeops_torch_ingress_ltnsr,</pre>	92
178	mlr_pipeops_nn_dropout,94
mlr_pipeops_torch_ingress_num, 180	mlr_pipeops_nn_elu,96
<pre>model_descriptor_to_learner, 202</pre>	mlr_pipeops_nn_flatten,98
<pre>model_descriptor_to_module, 203</pre>	${\tt mlr_pipeops_nn_gelu, 100}$
model_descriptor_union, 204	mlr_pipeops_nn_glu, 102
ModelDescriptor, 201	mlr_pipeops_nn_hardshrink, 103
nn_graph, 206	mlr_pipeops_nn_hardsigmoid, 105
TorchIngressToken, 216	${\tt mlr_pipeops_nn_hardtanh, 107}$
* Learner	mlr_pipeops_nn_head, 109
mlr_learners.mlp, 34	mlr_pipeops_nn_layer_norm, 110
mlr_learners.tab_resnet,37	mlr_pipeops_nn_leaky_relu, 112
mlr_learners.torch_featureless,41	mlr_pipeops_nn_linear, 114
mlr_learners_torch, 43	mlr_pipeops_nn_log_sigmoid, 116
mlr_learners_torch_image, 50	<pre>mlr_pipeops_nn_max_pool1d, 118</pre>

mlr_pipeops_nn_max_pool2d, 120	TorchLoss, 217
mlr_pipeops_nn_max_pool3d, 122	TorchOptimizer, 219
mlr_pipeops_nn_merge, 124	* datasets
mlr_pipeops_nn_merge_cat, 126	mlr3torch_callbacks, 20
mlr_pipeops_nn_merge_prod, 128	mlr3torch_losses, 20
mlr_pipeops_nn_merge_sum, 130	mlr3torch_optimizers, 21
mlr_pipeops_nn_prelu, 132	, 197
mlr_pipeops_nn_relu, 134	
mlr_pipeops_nn_relu6, 136	as.data.table, 20, 21
mlr_pipeops_nn_reshape, 138	as_data_descriptor,7
mlr_pipeops_nn_rrelu, 140	as_data_descriptor(), 15
mlr_pipeops_nn_selu, 142	as_lazy_tensor, 8
	as_torch_callback, 9, 10, 15, 20, 27, 29, 31
mlr_pipeops_nn_sigmoid, 143	34, 213, 224, 225
mlr_pipeops_nn_softmax, 145	as_torch_callbacks, 9, 10, 11, 15, 20, 21,
mlr_pipeops_nn_softplus, 147	27, 29, 31, 34, 213, 215, 218, 221,
mlr_pipeops_nn_softshrink, 149	224–227
mlr_pipeops_nn_softsign, 151	as_torch_callbacks(), 173
mlr_pipeops_nn_squeeze, 152	as_torch_loss, 10, 10, 11, 21, 213, 215, 218
mlr_pipeops_nn_tanh, 154	221, 225–227
mlr_pipeops_nn_tanhshrink, 156	as_torch_loss(), 183
mlr_pipeops_nn_threshold, 158	as_torch_optimizer, 10, 11, 11, 21, 213,
mlr_pipeops_nn_unsqueeze, 159	215, 218, 221, 225–227
mlr_pipeops_torch_ingress, 174	as_torch_optimizer(), 192
<pre>mlr_pipeops_torch_ingress_categ,</pre>	assert_lazy_tensor, 6
176	auto_device, 12
<pre>mlr_pipeops_torch_ingress_ltnsr,</pre>	
178	batchgetter_categ, 12
mlr_pipeops_torch_ingress_num, 180	batchgetter_categ(), 176
mlr_pipeops_torch_loss, 182	batchgetter_num, 13
mlr_pipeops_torch_model, 184	batchgetter_num(), 181
<pre>mlr_pipeops_torch_model_classif,</pre>	11b1+ 0 10 12 20 27 20 21 24
187	callback_set, 9, 10, 13, 20, 27, 29, 31, 34,
mlr_pipeops_torch_model_regr, 189	213, 224, 225
* PipeOp	callback_set(), 26, 221, 223
mlr_pipeops_module, 62	callbacks, 44
mlr_pipeops_torch_callbacks, 172	CallbackSet, 13, 14, 25, 32, 202, 211, 221,
mlr_pipeops_torch_optimizer, 191	223
* Torch Descriptor	CallbackSet (mlr_callback_set), 25
as_torch_callbacks, 10	CallbackSetCheckpoint
as_torch_loss, 10	<pre>(mlr_callback_set.checkpoint),</pre>
as_torch_optimizer, 11	28
mlr3torch_losses, 20	CallbackSetHistory
mlr3torch_optimizers, 21	(mlr_callback_set.history), 29
t_clbk, 224	CallbackSetProgress
t_loss, 225	<pre>(mlr_callback_set.progress), 30</pre>
t_opt, 226	ContextTorch, 26
TorchCallback, 211	ContextTorch (mlr_context_torch), 32
TorchDescriptor, 213	data.table, 20, 21
10. 6106361 19601, 213	GG GG CG C

data.table::data.table(), 23, 24	mlr3::lrns(), 224-226
DataBackend, 199, 200	mlr3::Task, 43, 161
DataBackendLazy, 199, 200	mlr3::TaskClassif, 198
DataBackendLazy (mlr_backends_lazy), 22	mlr3misc::Dictionary, 20
DataDescriptor, 7, 15, 18, 19	mlr3pipelines::Graph, 15, 62
dataset, 49, 210	mlr3pipelines::Pipe0p, 62, 63, 66, 68, 70,
datasets::iris, 198	72, 74, 76, 78, 80, 82, 84, 86, 89, 91
dictionary_sugar_get, 225, 226	93, 95, 97, 99, 100, 102, 104, 106,
dictionary_sugar_get(), 225	107, 109, 111, 113, 115, 117, 119,
200000000000000000000000000000000000000	121, 123, 125, 127, 129, 131, 133,
feature union, <i>166</i> , <i>204</i>	135, 137, 139, 140, 142, 144, 146,
,, .	148, 149, 151, 153, 155, 156, 158,
Graph, 15, 16, 19, 78, 166, 168, 201, 202, 206	160, 163, 168, 173, 174, 176, 178,
graph, <i>167</i>	
8. 56	181, 183, 186, 188, 190, 191
is_lazy_tensor, 17	mlr3pipelines::PipeOpLearner, 186, 188, 190
1 + 9 15 19 10 22 24 50 62	mlr3pipelines::PipeOpTaskPreproc, <i>163</i>
lazy_tensor, 8, 15, 18, 19, 22, 34, 50, 62,	mlr3torch (mlr3torch-package), 5
161, 178	mlr3torch-package, 5
lazy_tensor(), 18	mlr3torch::CallbackSet, 28-30
Learner, 32–34, 37, 41, 203	mlr3torch::LearnerTorch, 35, 37, 39, 41,
LearnerTorch, 26, 27, 32, 35, 37, 41, 50, 51, 187, 189	50, 52
LearnerTorch (mlr_learners_torch), 43	mlr3torch::LearnerTorchImage, 39
LearnerTorchFeatureless	mlr3torch::PipeOpTorch, 66, 68, 70, 72, 74
<pre>(mlr_learners.torch_featureless),</pre>	76, 78, 80, 82, 84, 86, 89, 91, 93, 95
41	97, 99, 100, 102, 104, 106, 107, 109
LearnerTorchImage, 39	111, 113, 115, 117, 119, 121, 123,
LearnerTorchImage	125, 127, 129, 131, 133, 135, 137,
(mlr_learners_torch_image), 50	139, 140, 142, 144, 146, 148, 149,
LearnerTorchMLP (mlr_learners.mlp), 34	151, 153, 155, 156, 158, 160
LearnerTorchModel, 184, 186–189	mlr3torch::PipeOpTorchIngress, 176, 178
LearnerTorchModel	181
(mlr_learners_torch_model), 51	mlr3torch::PipeOpTorchMerge, 127, 129,
LearnerTorchTabResNet	131
(mlr_learners.tab_resnet), 37	mlr3torch::PipeOpTorchModel, 188, 190
LearnerTorchVision	mlr3torch::TorchDescriptor, 212, 217,
	220
(mlr_learners.torchvision), 39	mlr3torch_callbacks, 9, 10, 15, 20, 21, 27,
loss, 44	29, 31, 34, 211, 213, 224, 225, 227
1rn(), 34, 37, 41	mlr3torch_losses, 10, 11, 20, 20, 21, 213,
	215, 217, 218, 221, 225–227
materialize, 18	
materialize(), 15	mlr3torch_optimizers, 10, 11, 20, 21, 21, 21, 21, 21, 21, 21, 21, 21, 22, 23, 23, 23, 23, 23, 23, 23, 23, 23
Measure, 32–34, 44, 185	213, 215, 218, 219, 221, 225–227
mlr3::as_prediction_data(),46	mlr_backends_lazy, 22
mlr3::col_info(), 22	mlr_callback_set, 9, 10, 15, 20, 25, 29, 31,
mlr3::DataBackend, 22	34, 213, 224, 225
mlr3::Learner, 35, 37, 39, 41, 46, 50, 52	mlr_callback_set.checkpoint, 9, 10, 15,
mlr3::lrn(), 224–226	20, 27, 28, 31, 34, 213, 224, 225

mlr_callback_set.history, 29	96, 98, 99, 101, 103, 105, 106, 108,
mlr_callback_set.progress, 9, 10, 15, 20,	110, 112, 114, 115, 117, 119, 122,
27, 29, 30, 34, 213, 224, 225	124, 126, 128, 130, 132, 134, 136,
mlr_context_torch, 9, 10, 15, 20, 27, 29, 31,	137, 139, 141, 143, 145, 146, 148,
32, 213, 224, 225	150, 152, 154, 155, 157, 159, 161,
mlr_learners.mlp, 34, 38, 42, 49, 51, 53	175, 177, 179, 181, 183, 187, 188,
mlr_learners.tab_resnet, <i>36</i> , <i>37</i> , <i>42</i> , <i>49</i> ,	190
51, 53	mlr_pipeops_nn_avg_pool3d, 66, 68, 69, 73,
mlr_learners.torch_featureless, 36, 38,	75, 77, 78, 80, 83, 85, 87, 89, 91, 94,
41, 49, 51, 53	96, 98, 99, 101, 103, 105, 106, 108,
mlr_learners.torchvision, 39	110, 112, 114, 115, 117, 119, 122,
mlr_learners_torch, 36, 38, 42, 43, 51, 53	124, 126, 128, 130, 132, 134, 136,
mlr_learners_torch_image, 36, 38, 42, 49,	137, 139, 141, 143, 145, 146, 148,
50, 53	150, 152, 154, 155, 157, 159, 161,
mlr_learners_torch_model, 36, 38, 42, 49,	175, 177, 179, 181, 183, 187, 188,
51, 51, 64, 169, 176, 177, 179, 181,	190
202–206, 216	$mlr_pipeops_nn_batch_norm1d, 66, 68, 71,$
mlr_pipeops, 205	71, 75, 77, 78, 80, 83, 85, 87, 89, 91,
mlr_pipeops_augment_center_crop, 54	94, 96, 98, 99, 101, 103, 105, 106,
mlr_pipeops_augment_color_jitter, 54	108, 110, 112, 114, 115, 117, 119,
mlr_pipeops_augment_crop, 55	122, 124, 126, 128, 130, 132, 134,
mlr_pipeops_augment_hflip, 55	136, 137, 139, 141, 143, 145, 146,
mlr_pipeops_augment_random_affine, 56	148, 150, 152, 154, 155, 157, 159,
mlr_pipeops_augment_random_choice, 57	161, 175, 177, 179, 181, 183, 187,
mlr_pipeops_augment_random_crop, 57	188, 190
<pre>mlr_pipeops_augment_random_horizontal_flip,</pre>	mlr_pipeops_nn_batch_norm2d, 66, 68, 71,
58	73, 73, 77, 78, 80, 83, 85, 87, 89, 91,
mlr_pipeops_augment_random_order, 58	94, 96, 98, 99, 101, 103, 105, 106,
mlr_pipeops_augment_random_resized_crop,	108, 110, 112, 114, 115, 117, 119,
59	122, 124, 126, 128, 130, 132, 134,
mlr_pipeops_augment_random_vertical_flip,	136, 137, 139, 141, 143, 145, 146,
60	148, 150, 152, 154, 155, 157, 159,
mlr_pipeops_augment_resized_crop, 60	161, 175, 177, 179, 181, 183, 187, 188, 190
mlr_pipeops_augment_rotate, 61	
mlr_pipeops_augment_vflip, 61	mlr_pipeops_nn_batch_norm3d, 66, 68, 71,
mlr_pipeops_module, 53, 62, 169, 173, 176,	73, 75, 75, 78, 80, 83, 85, 87, 89, 91,
177, 179, 181, 192, 202–206, 216	94, 96, 98, 99, 101, 103, 105, 106,
mlr_pipeops_nn_avg_pool1d, 65, 68, 71, 73,	108, 110, 112, 114, 115, 117, 119,
75, 77, 78, 80, 83, 85, 87, 89, 91, 94,	122, 124, 126, 128, 130, 132, 134, 136, 137, 139, 141, 143, 145, 146,
96, 98, 99, 101, 103, 105, 106, 108,	130, 137, 139, 141, 143, 143, 140, 148, 150, 152, 154, 155, 157, 159,
110, 112, 114, 115, 117, 119, 122,	161, 175, 177, 179, 181, 183, 187,
124, 126, 128, 130, 132, 134, 136,	188, 190
137, 139, 141, 143, 145, 146, 148,	
150, 152, 154, 155, 157, 159, 161, 175, 177, 179, 181, 183, 187, 188,	mlr_pipeops_nn_block, 66, 68, 71, 73, 75, 77, 77, 80, 83, 85, 87, 89, 91, 94, 96,
173, 177, 179, 161, 163, 167, 166,	98, 99, 101, 103, 105, 106, 108, 110,
mlr_pipeops_nn_avg_pool2d, 66, 67, 71, 73,	112, 114, 115, 117, 119, 122, 124,
75, 77, 78, 80, 83, 85, 87, 89, 91, 94.	126, 128, 130, 132, 134, 136, 137,

```
139, 141, 143, 145, 146, 148, 150,
                                                                  119, 122, 124, 126, 128, 130, 132,
         152, 154, 155, 157, 159, 161, 175,
                                                                  134, 136, 137, 139, 141, 143, 145,
          177, 179, 182, 183, 187, 188, 190
                                                                  146, 148, 150, 152, 154, 155, 157,
                                                                  159, 161, 175, 177, 179, 182, 183,
mlr_pipeops_nn_celu, 66, 68, 71, 73, 75, 77,
                                                                  187, 188, 190
          78, 79, 83, 85, 87, 89, 91, 94, 96, 98,
         99, 101, 103, 105, 106, 108, 110,
                                                       mlr_pipeops_nn_conv_transpose3d, 66, 68,
          112, 114, 115, 117, 119, 122, 124,
                                                                  71, 73, 75, 77, 78, 80, 83, 85, 87, 89,
          126, 128, 130, 132, 134, 136, 137,
                                                                  91, 92, 96, 98, 99, 101, 103, 105,
         139, 141, 143, 145, 146, 148, 150,
                                                                  106, 108, 110, 112, 114, 115, 117,
         152, 154, 155, 157, 159, 161, 175,
                                                                  119, 122, 124, 126, 128, 130, 132,
          177, 179, 182, 183, 187, 188, 190
                                                                  134, 136, 137, 139, 141, 143, 145,
                                                                  146, 148, 150, 152, 154, 155, 157,
mlr_pipeops_nn_conv1d, 66, 68, 71, 73, 75,
                                                                  159, 161, 176, 177, 179, 182, 183,
          77, 78, 80, 81, 85, 87, 89, 91, 94, 96,
                                                                  187, 188, 190
          98, 99, 101, 103, 105, 106, 108, 110,
         112, 114, 115, 117, 119, 122, 124,
                                                       mlr_pipeops_nn_dropout, 66, 68, 71, 73, 75,
         126, 128, 130, 132, 134, 136, 137,
                                                                  77, 78, 80, 83, 85, 87, 89, 91, 94, 94,
         139, 141, 143, 145, 146, 148, 150,
                                                                  98, 99, 101, 103, 105, 106, 108, 110,
          152, 154, 155, 157, 159, 161, 175,
                                                                  112, 114, 115, 117, 119, 122, 124,
          177, 179, 182, 183, 187, 188, 190
                                                                  126, 128, 130, 132, 134, 136, 137,
                                                                  139, 141, 143, 145, 146, 148, 150,
mlr_pipeops_nn_conv2d, 66, 68, 71, 73, 75,
                                                                  152, 154, 155, 157, 159, 161, 176,
          77, 78, 80, 83, 83, 87, 89, 91, 94, 96,
                                                                  177, 179, 182, 183, 187, 188, 190
         98, 99, 101, 103, 105, 106, 108, 110,
         112, 114, 115, 117, 119, 122, 124,
                                                       mlr_pipeops_nn_elu, 66, 68, 71, 73, 75, 77,
                                                                  78, 80, 83, 85, 87, 89, 91, 94, 96, 96,
          126, 128, 130, 132, 134, 136, 137,
          139, 141, 143, 145, 146, 148, 150,
                                                                  99, 101, 103, 105, 106, 108, 110,
          152, 154, 155, 157, 159, 161, 175,
                                                                  112, 114, 115, 117, 119, 122, 124,
          177, 179, 182, 183, 187, 188, 190
                                                                  126, 128, 130, 132, 134, 136, 137,
                                                                  139, 141, 143, 145, 146, 148, 150,
mlr_pipeops_nn_conv3d, 66, 68, 71, 73, 75,
                                                                  152, 154, 155, 157, 159, 161, 176,
          77, 78, 80, 83, 85, 85, 89, 91, 94, 96,
                                                                  177, 179, 182, 183, 187, 188, 190
          98, 99, 101, 103, 105, 106, 108, 110,
         112, 114, 115, 117, 119, 122, 124,
                                                       mlr_pipeops_nn_flatten, 66, 68, 71, 73, 75,
         126, 128, 130, 132, 134, 136, 137,
                                                                  77, 78, 80, 83, 85, 87, 89, 91, 94, 96,
         139, 141, 143, 145, 146, 148, 150,
                                                                  98, 98, 101, 103, 105, 106, 108, 110,
          152, 154, 155, 157, 159, 161, 175,
                                                                  112, 114, 115, 117, 119, 122, 124,
         177, 179, 182, 183, 187, 188, 190
                                                                  126, 128, 130, 132, 134, 136, 137,
                                                                  139, 141, 143, 145, 146, 148, 150,
mlr_pipeops_nn_conv_transpose1d, 66, 68,
                                                                  152, 154, 155, 157, 159, 161, 176,
          71, 73, 75, 77, 78, 80, 83, 85, 87, 87,
                                                                  177, 179, 182, 183, 187, 188, 190
         91, 94, 96, 98, 99, 101, 103, 105,
         106, 108, 110, 112, 114, 115, 117,
                                                       mlr_pipeops_nn_gelu, 66, 68, 71, 73, 75, 77,
                                                                  78, 80, 83, 85, 87, 89, 91, 94, 96, 98,
         119, 122, 124, 126, 128, 130, 132,
         134, 136, 137, 139, 141, 143, 145,
                                                                  99, 100, 103, 105, 106, 108, 110,
         146, 148, 150, 152, 154, 155, 157,
                                                                  112, 114, 115, 117, 119, 122, 124,
         159, 161, 175, 177, 179, 182, 183,
                                                                  126, 128, 130, 132, 134, 136, 137,
          187, 188, 190
                                                                  139, 141, 143, 145, 146, 148, 150,
                                                                  152, 154, 155, 157, 159, 161, 176,
mlr_pipeops_nn_conv_transpose2d, 66, 68,
                                                                  177, 179, 182, 183, 187, 188, 190
         71, 73, 75, 77, 78, 80, 83, 85, 87, 89,
         90, 94, 96, 98, 99, 101, 103, 105,
                                                       mlr_pipeops_nn_glu, 66, 68, 71, 73, 75, 77,
         106, 108, 110, 112, 114, 115, 117,
                                                                  78, 80, 83, 85, 87, 89, 92, 94, 96, 98,
```

```
99, 101, 102, 105, 106, 108, 110,
                                                                  176, 177, 179, 182, 183, 187, 188,
         112, 114, 115, 117, 119, 122, 124,
          126, 128, 130, 132, 134, 136, 137,
                                                        mlr_pipeops_nn_leaky_relu, 66, 69, 71, 73,
          139, 141, 143, 145, 146, 148, 150,
                                                                  75, 77, 78, 80, 83, 85, 87, 89, 92, 94,
          152, 154, 155, 157, 159, 161, 176,
                                                                  96, 98, 99, 101, 103, 105, 106, 108,
          177, 179, 182, 183, 187, 188, 190
                                                                  110, 112, 112, 115, 117, 119, 122,
mlr_pipeops_nn_hardshrink, 66, 68, 71, 73,
                                                                  124, 126, 128, 130, 132, 134, 136,
          75, 77, 78, 80, 83, 85, 87, 89, 92, 94,
                                                                  137, 139, 141, 143, 145, 146, 148,
          96, 98, 99, 101, 103, 103, 106, 108,
                                                                  150, 152, 154, 155, 157, 159, 161,
                                                                  176, 177, 179, 182, 183, 187, 188,
          110, 112, 114, 115, 117, 119, 122,
                                                                  190
          124, 126, 128, 130, 132, 134, 136,
          137, 139, 141, 143, 145, 146, 148,
                                                        mlr_pipeops_nn_linear, 66, 69, 71, 73, 75,
          150, 152, 154, 155, 157, 159, 161,
                                                                  77, 78, 80, 83, 85, 87, 89, 92, 94, 96,
          176, 177, 179, 182, 183, 187, 188,
                                                                  98, 99, 101, 103, 105, 106, 108, 110,
                                                                  112, 114, 114, 117, 120, 122, 124,
mlr_pipeops_nn_hardsigmoid, 66, 68, 71,
                                                                  126, 128, 130, 132, 134, 136, 137,
                                                                  139, 141, 143, 145, 146, 148, 150,
          73, 75, 77, 78, 80, 83, 85, 87, 89, 92,
          94, 96, 98, 99, 101, 103, 105, 105,
                                                                  152, 154, 155, 157, 159, 161, 176,
                                                                  177, 179, 182, 183, 187, 188, 190
          108, 110, 112, 114, 115, 117, 119,
          122, 124, 126, 128, 130, 132, 134,
                                                        mlr_pipeops_nn_log_sigmoid, 66, 69, 71,
          136, 137, 139, 141, 143, 145, 146,
                                                                  73, 75, 77, 78, 80, 83, 85, 87, 89, 92,
          148, 150, 152, 154, 155, 157, 159,
                                                                  94, 96, 98, 99, 101, 103, 105, 106,
          161, 176, 177, 179, 182, 183, 187,
                                                                  108, 110, 112, 114, 116, 116, 120,
          188, 190
                                                                  122, 124, 126, 128, 130, 132, 134,
                                                                  136, 137, 139, 141, 143, 145, 146,
mlr_pipeops_nn_hardtanh, 66, 68, 71, 73,
                                                                  148, 150, 152, 154, 155, 157, 159,
          75, 77, 78, 80, 83, 85, 87, 89, 92, 94,
                                                                  161, 176, 177, 179, 182, 183, 187,
          96, 98, 99, 101, 103, 105, 106, 107,
                                                                  188, 190
          110, 112, 114, 115, 117, 119, 122,
         124, 126, 128, 130, 132, 134, 136,
                                                        mlr_pipeops_nn_max_pool1d, 66, 69, 71, 73,
          137, 139, 141, 143, 145, 146, 148,
                                                                  75, 77, 78, 80, 83, 85, 87, 89, 92, 94,
          150, 152, 154, 155, 157, 159, 161,
                                                                  96, 98, 99, 101, 103, 105, 106, 108,
          176, 177, 179, 182, 183, 187, 188,
                                                                  110, 112, 114, 116, 117, 118, 122,
          190
                                                                  124, 126, 128, 130, 132, 134, 136,
                                                                  137, 139, 141, 143, 145, 146, 148,
mlr_pipeops_nn_head, 66, 68, 71, 73, 75, 77,
                                                                  150, 152, 154, 155, 157, 159, 161,
          78, 80, 83, 85, 87, 89, 92, 94, 96, 98,
                                                                  176, 177, 179, 182, 183, 187, 188,
          99, 101, 103, 105, 106, 108, 109,
                                                                  190
          112, 114, 115, 117, 119, 122, 124,
          126, 128, 130, 132, 134, 136, 137,
                                                        mlr_pipeops_nn_max_pool2d, 66, 69, 71, 73,
          139, 141, 143, 145, 146, 148, 150,
                                                                  75, 77, 78, 80, 83, 85, 87, 89, 92, 94,
          152, 154, 155, 157, 159, 161, 176,
                                                                  96, 98, 99, 101, 103, 105, 106, 108,
          177, 179, 182, 183, 187, 188, 190
                                                                  110, 112, 114, 116, 117, 120, 120,
                                                                  124, 126, 128, 130, 132, 134, 136,
mlr_pipeops_nn_layer_norm, 66, 69, 71, 73,
                                                                  137, 139, 141, 143, 145, 146, 148,
          75, 77, 78, 80, 83, 85, 87, 89, 92, 94,
                                                                  150, 152, 154, 155, 157, 159, 161,
          96, 98, 99, 101, 103, 105, 106, 108,
                                                                  176, 177, 179, 182, 183, 187, 188,
          110, 110, 114, 115, 117, 119, 122,
                                                                  190
          124, 126, 128, 130, 132, 134, 136,
                                                        mlr_pipeops_nn_max_pool3d, 66, 69, 71, 73,
          137, 139, 141, 143, 145, 146, 148,
          150, 152, 154, 155, 157, 159, 161,
                                                                  75, 77, 78, 81, 83, 85, 87, 89, 92, 94,
```

150, 152, 154, 155, 157, 159, 161,

96, 98, 99, 101, 103, 105, 106, 108,

```
110, 112, 114, 116, 117, 120, 122,
                                                                  176, 177, 179, 182, 183, 187, 188,
          122, 126, 128, 130, 132, 134, 136,
                                                                  190
          137, 139, 141, 143, 145, 146, 148,
                                                        mlr_pipeops_nn_relu, 66, 69, 71, 73, 75, 77,
          150, 152, 154, 155, 157, 159, 161,
                                                                  79, 81, 83, 85, 87, 89, 92, 94, 96, 98,
          176, 177, 179, 182, 183, 187, 188,
                                                                  100, 101, 103, 105, 106, 108, 110,
          190
                                                                  112, 114, 116, 117, 120, 122, 124,
mlr_pipeops_nn_merge, 66, 69, 71, 73, 75,
                                                                  126, 128, 130, 132, 134, 134, 137,
          77, 78, 81, 83, 85, 87, 89, 92, 94, 96,
                                                                  139, 141, 143, 145, 146, 148, 150,
                                                                  152, 154, 155, 157, 159, 161, 176,
          98, 99, 101, 103, 105, 106, 108, 110,
          112, 114, 116, 117, 120, 122, 124,
                                                                  177, 179, 182, 183, 187, 188, 190
          124, 128, 130, 132, 134, 136, 137,
                                                        mlr_pipeops_nn_relu6, 66, 69, 71, 73, 75,
          139, 141, 143, 145, 146, 148, 150,
                                                                  77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
          152, 154, 155, 157, 159, 161, 176,
                                                                  98, 100, 101, 103, 105, 106, 108,
          177, 179, 182, 183, 187, 188, 190
                                                                  110, 112, 114, 116, 117, 120, 122,
mlr_pipeops_nn_merge_cat, 66, 69, 71, 73,
                                                                  124, 126, 128, 130, 132, 134, 136,
                                                                  136, 139, 141, 143, 145, 146, 148,
          75, 77, 78, 81, 83, 85, 87, 89, 92, 94,
          96, 98, 99, 101, 103, 105, 106, 108,
                                                                  150, 152, 154, 155, 157, 159, 161,
                                                                  176, 177, 179, 182, 183, 187, 188,
          110, 112, 114, 116, 117, 120, 122,
          124, 126, 126, 130, 132, 134, 136,
          137, 139, 141, 143, 145, 146, 148,
                                                        mlr_pipeops_nn_reshape, 66, 69, 71, 73, 75,
          150, 152, 154, 155, 157, 159, 161,
                                                                  77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
          176, 177, 179, 182, 183, 187, 188,
                                                                  98, 100, 101, 103, 105, 106, 108,
          190
                                                                  110, 112, 114, 116, 117, 120, 122,
                                                                  124, 126, 128, 130, 132, 134, 136,
mlr_pipeops_nn_merge_prod, 66, 69, 71, 73,
                                                                  137, 138, 141, 143, 145, 147, 148,
          75, 77, 78, 81, 83, 85, 87, 89, 92, 94,
                                                                  150, 152, 154, 155, 157, 159, 161,
          96, 98, 99, 101, 103, 105, 106, 108,
                                                                  176, 177, 179, 182, 183, 187, 188,
          110, 112, 114, 116, 117, 120, 122,
                                                                  190
         124, 126, 128, 128, 132, 134, 136,
          137, 139, 141, 143, 145, 146, 148,
                                                        mlr_pipeops_nn_rrelu, 66, 69, 71, 73, 75,
          150, 152, 154, 155, 157, 159, 161,
                                                                  77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
          176, 177, 179, 182, 183, 187, 188,
                                                                  98, 100, 101, 103, 105, 106, 108,
          190
                                                                  110, 112, 114, 116, 117, 120, 122,
                                                                  124, 126, 128, 130, 132, 134, 136,
mlr_pipeops_nn_merge_sum, 66, 69, 71, 73,
                                                                  138, 139, 140, 143, 145, 147, 148,
          75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
                                                                  150, 152, 154, 155, 157, 159, 161,
          96, 98, 100, 101, 103, 105, 106, 108,
                                                                  176, 177, 179, 182, 183, 187, 188,
          110, 112, 114, 116, 117, 120, 122,
                                                                  190
          124, 126, 128, 130, 130, 134, 136,
          137, 139, 141, 143, 145, 146, 148,
                                                        mlr_pipeops_nn_selu, 67, 69, 71, 73, 75, 77,
          150, 152, 154, 155, 157, 159, 161,
                                                                  79, 81, 83, 85, 87, 89, 92, 94, 96, 98,
          176, 177, 179, 182, 183, 187, 188,
                                                                  100, 101, 103, 105, 106, 108, 110,
                                                                  112, 114, 116, 117, 120, 122, 124,
                                                                  126, 128, 130, 132, 134, 136, 138,
mlr_pipeops_nn_prelu, 66, 69, 71, 73, 75,
                                                                  139, 141, 142, 145, 147, 148, 150,
          77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
                                                                  152, 154, 155, 157, 159, 161, 176,
          98, 100, 101, 103, 105, 106, 108,
                                                                  177, 179, 182, 183, 187, 188, 190
          110, 112, 114, 116, 117, 120, 122,
          124, 126, 128, 130, 132, 132, 136,
                                                        mlr_pipeops_nn_sigmoid, 67, 69, 71, 73, 75,
          137, 139, 141, 143, 145, 146, 148,
                                                                  77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
```

```
98, 100, 101, 103, 105, 106, 108,
                                                                 138, 139, 141, 143, 145, 147, 148,
         110, 112, 114, 116, 117, 120, 122,
                                                                 150, 152, 152, 156, 157, 159, 161,
                                                                 176, 177, 179, 182, 183, 187, 189,
         124, 126, 128, 130, 132, 134, 136,
          138, 139, 141, 143, 143, 147, 148,
                                                                 190
          150, 152, 154, 155, 157, 159, 161,
                                                       mlr_pipeops_nn_tanh, 67, 69, 71, 73, 75, 77,
          176, 177, 179, 182, 183, 187, 188,
                                                                 79, 81, 83, 85, 87, 89, 92, 94, 96, 98,
          190
                                                                 100, 101, 103, 105, 107, 108, 110,
mlr_pipeops_nn_softmax, 67, 69, 71, 73, 75,
                                                                 112, 114, 116, 117, 120, 122, 124,
          77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
                                                                 126, 128, 130, 132, 134, 136, 138,
                                                                 139, 141, 143, 145, 147, 148, 150,
         98, 100, 101, 103, 105, 107, 108,
                                                                 152, 154, 154, 157, 159, 161, 176,
         110, 112, 114, 116, 117, 120, 122,
                                                                 177, 179, 182, 183, 187, 189, 190
          124, 126, 128, 130, 132, 134, 136,
          138, 139, 141, 143, 145, 145, 148,
                                                       mlr_pipeops_nn_tanhshrink, 67, 69, 71, 73,
          150, 152, 154, 156, 157, 159, 161,
                                                                 75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
          176, 177, 179, 182, 183, 187, 188,
                                                                 96, 98, 100, 101, 103, 105, 107, 108,
                                                                 110, 112, 114, 116, 117, 120, 122,
                                                                 124, 126, 128, 130, 132, 134, 136,
mlr_pipeops_nn_softplus, 67, 69, 71, 73,
                                                                 138, 139, 141, 143, 145, 147, 148,
         75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
                                                                 150, 152, 154, 156, 156, 159, 161,
          96, 98, 100, 101, 103, 105, 107, 108,
                                                                 176, 177, 179, 182, 183, 187, 189,
         110, 112, 114, 116, 117, 120, 122,
                                                                 190
          124, 126, 128, 130, 132, 134, 136,
         138, 139, 141, 143, 145, 147, 147,
                                                       mlr_pipeops_nn_threshold, 67, 69, 71, 73,
         150, 152, 154, 156, 157, 159, 161,
                                                                 75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
                                                                 96, 98, 100, 101, 103, 105, 107, 108,
          176, 177, 179, 182, 183, 187, 188,
                                                                 110, 112, 114, 116, 117, 120, 122,
                                                                 124, 126, 128, 130, 132, 134, 136,
mlr_pipeops_nn_softshrink, 67, 69, 71, 73,
                                                                 138, 139, 141, 143, 145, 147, 148,
          75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
                                                                 150, 152, 154, 156, 157, 158, 161,
         96, 98, 100, 101, 103, 105, 107, 108,
                                                                 176, 177, 179, 182, 183, 187, 189,
         110, 112, 114, 116, 117, 120, 122,
                                                                 190
         124, 126, 128, 130, 132, 134, 136,
                                                       mlr_pipeops_nn_unsqueeze, 67, 69, 71, 73,
          138, 139, 141, 143, 145, 147, 148,
                                                                 75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
          149, 152, 154, 156, 157, 159, 161,
          176, 177, 179, 182, 183, 187, 188,
                                                                 96, 98, 100, 101, 103, 105, 107, 108,
                                                                 110, 112, 114, 116, 117, 120, 122,
          190
                                                                 124, 126, 128, 130, 132, 134, 136,
mlr_pipeops_nn_softsign, 67, 69, 71, 73,
                                                                 138, 139, 141, 143, 145, 147, 148,
          75, 77, 79, 81, 83, 85, 87, 89, 92, 94,
                                                                 150, 152, 154, 156, 157, 159, 159,
          96, 98, 100, 101, 103, 105, 107, 108,
                                                                 176, 177, 179, 182, 184, 187, 189,
         110, 112, 114, 116, 117, 120, 122,
                                                                 190
         124, 126, 128, 130, 132, 134, 136,
                                                       mlr_pipeops_preproc_torch, 161
         138, 139, 141, 143, 145, 147, 148,
                                                       mlr_pipeops_torch, 53, 64, 166, 176, 177,
          150, 151, 154, 156, 157, 159, 161,
          176, 177, 179, 182, 183, 187, 188,
                                                                 179, 181, 202–206, 216
          190
                                                       mlr_pipeops_torch_callbacks, 64, 172,
                                                                 184, 192, 202, 205
mlr_pipeops_nn_squeeze, 67, 69, 71, 73, 75,
          77, 79, 81, 83, 85, 87, 89, 92, 94, 96,
                                                       mlr_pipeops_torch_ingress, 53, 64, 67, 69,
         98, 100, 101, 103, 105, 107, 108,
                                                                 71, 73, 75, 77, 79, 81, 83, 85, 87, 89,
          110, 112, 114, 116, 117, 120, 122,
                                                                 92, 94, 96, 98, 100, 101, 103, 105,
          124, 126, 128, 130, 132, 134, 136,
                                                                 107, 108, 110, 112, 114, 116, 117,
```

120, 122, 124, 126, 128, 130, 132,	110, 112, 114, 116, 117, 120, 122,
134, 136, 138, 139, 141, 143, 145,	124, 126, 128, 130, 132, 134, 136,
147, 148, 150, 152, 154, 156, 157,	138, 139, 141, 143, 145, 147, 148,
159, 161, 169, 174, 177, 179, 181,	150, 152, 154, 156, 157, 159, 161,
182, 184, 187, 189, 190, 202–206,	176, 177, 179, 182, 184, 184, 189,
216	190
mlr_pipeops_torch_ingress_categ, 53, 64,	mlr_pipeops_torch_model_classif, 67, 69,
67, 69, 71, 73, 75, 77, 79, 81, 83, 85,	71, 73, 75, 77, 79, 81, 83, 85, 87, 89,
87, 89, 92, 94, 96, 98, 100, 101, 103,	92, 94, 96, 98, 100, 101, 103, 105,
105, 107, 108, 110, 112, 114, 116,	107, 108, 110, 112, 114, 116, 117,
117, 120, 122, 124, 126, 128, 130,	120, 122, 124, 126, 128, 130, 132,
132, 134, 136, 138, 139, 141, 143,	134, 136, 138, 139, 141, 143, 145,
145, 147, 148, 150, 152, 154, 156,	147, 148, 150, 152, 154, 156, 157,
157, 159, 161, 169, 176, 176, 179,	159, 161, 176, 177, 179, 182, 184,
181, 182, 184, 187, 189, 190,	187, 187, 190
202–206, 216	mlr_pipeops_torch_model_regr, 67, 69, 71,
mlr_pipeops_torch_ingress_ltnsr, 53, 64,	73, 75, 77, 79, 81, 83, 85, 87, 89, 92,
67, 69, 71, 73, 75, 77, 79, 81, 83, 85,	94, 96, 98, 100, 101, 103, 105, 107,
87, 89, 92, 94, 96, 98, 100, 101, 103,	108, 110, 112, 114, 116, 117, 120,
105, 107, 108, 110, 112, 114, 116,	122, 124, 126, 128, 130, 132, 134,
117, 120, 122, 124, 126, 128, 130,	136, 138, 139, 141, 143, 145, 147,
132, 134, 136, 138, 139, 141, 143,	148, 150, 152, 154, 156, 157, 159,
145, 147, 148, 150, 152, 154, 156,	161, 176, 177, 179, 182, 184, 187,
	189, 189
157, 159, 161, 169, 176, 177, 178,	mlr_pipeops_torch_optimizer, 64, 173,
181, 182, 184, 187, 189, 190, 202–206, 216	184, 191, 202, 205
	mlr_pipeops_trafo_adjust_brightness,
mlr_pipeops_torch_ingress_num, 53, 64,	193
67, 69, 71, 73, 75, 77, 79, 81, 83, 85,	mlr_pipeops_trafo_adjust_gamma, 193
87, 89, 92, 94, 96, 98, 100, 101, 103,	mlr_pipeops_trafo_adjust_hue, 194
105, 107, 108, 110, 112, 114, 116,	mlr_pipeops_trafo_adjust_saturation,
117, 120, 122, 124, 126, 128, 130,	194
132, 134, 136, 138, 139, 141, 143,	mlr_pipeops_trafo_grayscale, 195
145, 147, 148, 150, 152, 154, 156,	
157, 159, 161, 169, 176, 177, 179,	mlr_pipeops_trafo_nop, 195
180, 184, 187, 189, 190, 202–206,	mlr_pipeops_trafo_normalize, 196
216	mlr_pipeops_trafo_pad, 196
mlr_pipeops_torch_loss, 67, 69, 71, 73, 75,	mlr_pipeops_trafo_reshape, 197
77, 79, 81, 83, 85, 87, 89, 92, 94, 96,	mlr_pipeops_trafo_resize, 197
98, 100, 101, 103, 105, 107, 108,	<pre>mlr_pipeops_trafo_rgb_to_grayscale,</pre>
110, 112, 114, 116, 117, 120, 122,	198
124, 126, 128, 130, 132, 134, 136,	<pre>mlr_reflections\$learner_predict_types,</pre>
138, 139, 141, 143, 145, 147, 148,	48, 51
150, 152, 154, 156, 157, 159, 161,	$mlr_reflections learner_properties, 48,$
173, 176, 177, 179, 182, 182, 187,	51
189, 190, 192, 202, 205	${\tt mlr_reflections\$task_feature_types}, {\tt 48},$
mlr_pipeops_torch_model, 67, 69, 71, 73,	175
75, 77, 79, 81, 83, 85, 87, 89, 92, 94,	mlr_tasks_lazy_iris, 198
	mir_casks_razy_rris, 170

mlr_tasks_tiny_imagenet, 200	ParamSet, 46–48, 50, 126, 164, 167, 168, 175,
model descriptor union, 167	209, 211, 213–215, 217–219
model_descriptor_to_learner, 53, 64, 169,	ParamUty, 219
176, 177, 179, 181, 202, 202,	PipeOp, 19, 109, 166, 169
204–206, 216	pipeop_preproc_torch, 161, 209
model_descriptor_to_learner(), 186, 188, 189	PipeOpModule, 15, 162, 166, 167, 169, 202, 206
model_descriptor_to_module, 53, 64, 169,	PipeOpModule (mlr_pipeops_module), 62
<i>176, 177, 179, 181, 201–203,</i> 203,	PipeOpNOP, 166, 202
205, 206, 216	PipeOpPreprocTorchAugmentCenterCrop
model_descriptor_union, 53, 64, 168, 169,	<pre>(mlr_pipeops_augment_center_crop),</pre>
173, 176, 177, 179, 181, 184, 192,	54
202–204, 204, 206, 216	PipeOpPreprocTorchAugmentColorJitter
ModelDescriptor, 53, 62, 64, 163, 166-169,	<pre>(mlr_pipeops_augment_color_jitter),</pre>
172, 173, 176, 177, 179, 181, 183,	54
184, 186, 188, 189, 191, 192, 201,	PipeOpPreprocTorchAugmentCrop
203–206, 211, 216, 217, 219	<pre>(mlr_pipeops_augment_crop), 55</pre>
module, 63	PipeOpPreprocTorchAugmentHflip
	<pre>(mlr_pipeops_augment_hflip), 55</pre>
network, 44	PipeOpPreprocTorchAugmentRandomAffine
nn, 205	<pre>(mlr_pipeops_augment_random_affine),</pre>
nn_avg_pool1d(), 66	56
nn_avg_pool2d(), 67	PipeOpPreprocTorchAugmentRandomChoice
nn_avg_pool3d(), 69	<pre>(mlr_pipeops_augment_random_choice),</pre>
nn_conv_transpose1d, 88	57
nn_conv_transpose2d, 90	PipeOpPreprocTorchAugmentRandomCrop
nn_conv_transpose3d, 92	<pre>(mlr_pipeops_augment_random_crop),</pre>
nn_graph, 53, 64, 169, 176, 177, 179, 181,	57
201–206, 206, 216	PipeOpPreprocTorchAugmentRandomHorizontalFlip
nn_linear, 166	<pre>(mlr_pipeops_augment_random_horizontal_flip)</pre>
nn_merge_cat, 207	58
nn_merge_cat(), <i>127</i>	PipeOpPreprocTorchAugmentRandomOrder
nn_merge_prod, 207	<pre>(mlr_pipeops_augment_random_order),</pre>
nn_merge_prod(), 129 nn_merge_sum, 207	58
nn_merge_sum(), <i>131</i>	PipeOpPreprocTorchAugmentRandomResizedCrop
nn module, 46, 52, 62, 63, 166, 167	<pre>(mlr_pipeops_augment_random_resized_crop), 59</pre>
nn_module(), 47, 51	
nn_relu, <i>35</i>	<pre>PipeOpPreprocTorchAugmentRandomVerticalFlip</pre>
nn_reshape, 208	(iiir_pipeops_augilient_randoil_verticai_fiip),
nn_reshape(), <i>138</i>	PipeOpPreprocTorchAugmentResizedCrop
nn_sequential, 98	(mlr_pipeops_augment_resized_crop),
nn_squeeze, 208	60
nn_squeeze(), <i>153</i>	PipeOpPreprocTorchAugmentRotate
nn_unsqueeze, 208	(mlr_pipeops_augment_rotate),
nn_unsqueeze(), 160	61
- Programme	PipeOpPreprocTorchAugmentVflip
optimizer, 44	(mlr_pipeops_augment_vflip), 61
•	(-

PipeUpPreproclorchirafoAdjustBrightness	PipeUpiorchAvgPool2D
<pre>(mlr_pipeops_trafo_adjust_brightness)</pre>	, (mlr_pipeops_nn_avg_pool2d), 67
193	PipeOpTorchAvgPool3D
PipeOpPreprocTorchTrafoAdjustGamma	(mlr_pipeops_nn_avg_pool3d), 69
<pre>(mlr_pipeops_trafo_adjust_gamma),</pre>	PipeOpTorchBatchNorm1D
193	<pre>(mlr_pipeops_nn_batch_norm1d),</pre>
PipeOpPreprocTorchTrafoAdjustHue	71
(mlr_pipeops_trafo_adjust_hue),	PipeOpTorchBatchNorm2D
194	<pre>(mlr_pipeops_nn_batch_norm2d),</pre>
PipeOpPreprocTorchTrafoAdjustSaturation	73
(mlr_pipeops_trafo_adjust_saturation)	
194	(mlr_pipeops_nn_batch_norm3d),
PipeOpPreprocTorchTrafoGrayscale	75
(mlr_pipeops_trafo_grayscale),	PipeOpTorchBlock
195	(mlr_pipeops_nn_block), 77
PipeOpPreprocTorchTrafoNop	PipeOpTorchCallbacks, 201
(mlr_pipeops_trafo_nop), 195	PipeOpTorchCallbacks
PipeOpPreprocTorchTrafoNormalize	<pre>(mlr_pipeops_torch_callbacks),</pre>
(mlr_pipeops_trafo_normalize),	172
196	PipeOpTorchCELU (mlr_pipeops_nn_celu),
	79
PipeOpPreprocTorchTrafoPad	
(mlr_pipeops_trafo_pad), 196	PipeOpTorchConv1D
PipeOpPreprocTorchTrafoReshape	(mlr_pipeops_nn_conv1d), 81
<pre>(mlr_pipeops_trafo_reshape), 197</pre>	PipeOpTorchConv2D
	(mlr_pipeops_nn_conv2d), 83
PipeOpPreprocTorchTrafoResize	PipeOpTorchConv3D
(mlr_pipeops_trafo_resize), 197	(mlr_pipeops_nn_conv3d), 85
PipeOpPreprocTorchTrafoRgbToGrayscale	PipeOpTorchConvTranspose1D
<pre>(mlr_pipeops_trafo_rgb_to_grayscale),</pre>	(mlr_pipeops_nn_conv_transpose1d)
198	87 Di
Pipe0pTaskPreproc, 162	PipeOpTorchConvTranspose2D
PipeOpTaskPreprocSimple, 162	(mlr_pipeops_nn_conv_transpose2d)
PipeOpTaskPreprocTorch, <i>54–62</i> , <i>193–198</i> ,	90
209, 210	PipeOpTorchConvTranspose3D
PipeOpTaskPreprocTorch	<pre>(mlr_pipeops_nn_conv_transpose3d)</pre>
<pre>(mlr_pipeops_preproc_torch),</pre>	92
161	PipeOpTorchDropout
PipeOpTorch, 62, 65, 67, 69, 71, 73, 75, 78,	(mlr_pipeops_nn_dropout), 94
79, 81, 83, 85, 88, 90, 92, 94, 96, 98,	PipeOpTorchELU (mlr_pipeops_nn_elu), 96
100, 102, 104, 105, 109, 111, 112,	PipeOpTorchFlatten
114, 116, 118, 120, 123, 125, 127,	(mlr_pipeops_nn_flatten), 98
129, 130, 133, 134, 136, 138, 140,	<pre>PipeOpTorchGELU (mlr_pipeops_nn_gelu),</pre>
142, 144, 145, 147, 149, 151, 153,	100
154, 156, 158, 160, 167, 174, 176,	PipeOpTorchGLU(mlr_pipeops_nn_glu), 102
178, 181, 182, 201, 204	PipeOpTorchHardShrink
PipeOpTorch (mlr_pipeops_torch), 166	<pre>(mlr_pipeops_nn_hardshrink),</pre>
PipeOpTorchAvgPool1D	103
(mlr_pipeops_nn_avg_pool1d), 65	PipeOpTorchHardSigmoid

(mir_pipeops_nn_nardsigmoid),	PipeUplorchMergeCat, 124
105	PipeOpTorchMergeCat
PipeOpTorchHardTanh	<pre>(mlr_pipeops_nn_merge_cat), 126</pre>
(mlr_pipeops_nn_hardtanh), 107	PipeOpTorchMergeProd, 124
PipeOpTorchHead, <i>167</i> , <i>169</i>	PipeOpTorchMergeProd
PipeOpTorchHead(mlr_pipeops_nn_head), 109	<pre>(mlr_pipeops_nn_merge_prod), 128</pre>
PipeOpTorchIngress, 62, 168, 201	PipeOpTorchMergeSum, 124
PipeOpTorchIngress	PipeOpTorchMergeSum
(mlr_pipeops_torch_ingress),	(mlr_pipeops_nn_merge_sum), 130
174	PipeOpTorchModel, <i>163</i>
PipeOpTorchIngressCategorical, 174	PipeOpTorchModel
PipeOpTorchIngressCategorical	(mlr_pipeops_torch_model), 184
<pre>(mlr_pipeops_torch_ingress_categ),</pre>	PipeOpTorchModelClassif
176	<pre>(mlr_pipeops_torch_model_classif),</pre>
PipeOpTorchIngressLazyTensor, 174	187
PipeOpTorchIngressLazyTensor	PipeOpTorchModelRegr
<pre>(mlr_pipeops_torch_ingress_ltnsr),</pre>	<pre>(mlr_pipeops_torch_model_regr),</pre>
178	189
PipeOpTorchIngressNumeric, <i>174</i>	PipeOpTorchOptimizer, 201
PipeOpTorchIngressNumeric	PipeOpTorchOptimizer
(mlr_pipeops_torch_ingress_num),	<pre>(mlr_pipeops_torch_optimizer),</pre>
180	191
PipeOpTorchLayerNorm	PipeOpTorchPReLU
(mlr_pipeops_nn_layer_norm),	(mlr_pipeops_nn_prelu), 132
110	PipeOpTorchReLU (mlr_pipeops_nn_relu),
PipeOpTorchLeakyReLU	134
(mlr_pipeops_nn_leaky_relu),	PipeOpTorchReLU6
112	(mlr_pipeops_nn_relu6), 136
PipeOpTorchLinear	PipeOpTorchReshape
(mlr_pipeops_nn_linear), 114	(mlr_pipeops_nn_reshape), 138
PipeOpTorchLogSigmoid	PipeOpTorchRReLU
(mlr_pipeops_nn_log_sigmoid),	(mlr_pipeops_nn_rrelu), 140
116	PipeOpTorchSELU (mlr_pipeops_nn_selu),
PipeOpTorchLoss, 201	142
PipeOpTorchLoss	PipeOpTorchSigmoid
<pre>(mlr_pipeops_torch_loss), 182</pre>	(mlr_pipeops_nn_sigmoid), 143
PipeOpTorchMaxPool1D	PipeOpTorchSoftmax
(mlr_pipeops_nn_max_pool1d),	(mlr_pipeops_nn_softmax), 145
118	PipeOpTorchSoftPlus
PipeOpTorchMaxPool2D	(mlr_pipeops_nn_softplus), 147
(mlr_pipeops_nn_max_pool2d),	PipeOpTorchSoftShrink
120	(mlr_pipeops_nn_softshrink),
PipeOpTorchMaxPool3D	149
(mlr_pipeops_nn_max_pool3d),	PipeOpTorchSoftSign
122	(mlr_pipeops_nn_softsign), 151
PipeOpTorchMerge	PipeOpTorchSqueeze
(mlr_pipeops_nn_merge), 124	(mlr_pipeops_nn_squeeze), 152
(p-p-0-p 50/, 12 ·	(p-p-0p0qu0020/, 102

PipeOplorchlanh (mir_pipeops_nn_tanh),	torch::nn_conv2d(), 84
154	torch::nn_conv3d(), 86
PipeOpTorchTanhShrink	torch::nn_dropout(),95
<pre>(mlr_pipeops_nn_tanhshrink),</pre>	torch::nn_elu(), <i>97</i>
156	torch::nn_flatten(),99
PipeOpTorchThreshold	torch::nn_gelu(), <i>100</i>
(mlr_pipeops_nn_threshold), 158	torch::nn_glu(), <i>102</i>
PipeOpTorchUnsqueeze	torch::nn_hardshrink(), 104
(mlr_pipeops_nn_unsqueeze), 159	torch::nn_hardsigmoid(), 106
16 00 00 00 05 00 40 41 45 50 50	torch::nn_hardswish(), 113
R6, 16, 23, 28, 33, 35, 38, 40, 41, 47, 50, 52,	torch::nn_hardtanh(), 107
63, 66, 68, 70, 72, 74, 76, 78, 80, 82,	<pre>torch::nn_layer_norm(), 111</pre>
84, 86, 89, 91, 93, 95, 97, 99, 101,	torch::nn_linear(), 109, 115
102, 104, 106, 108, 109, 111, 113,	<pre>torch::nn_log_sigmoid(), 116</pre>
115, 117, 119, 121, 123, 125, 127,	torch::nn_max_pool1d(), <i>119</i>
129, 131, 133, 135, 137, 139, 141,	torch::nn_max_pool2d(), <i>120</i>
142, 144, 146, 148, 150, 151, 153,	torch::nn_max_pool3d(), <i>122</i>
155, 157, 158, 160, 163, 168, 173,	torch::nn_module, 32, 34, 46
175, 177, 178, 181, 183, 186, 188,	torch::nn_prelu(), <i>133</i>
190, 192, 212, 214, 217, 220	torch::nn_relu(), <i>135</i>
R6::R6Class, 198	torch::nn_relu6(), <i>137</i>
R6Class, 14, 54–62, 193–198, 210, 223	torch::nn_rrelu(), <i>140</i>
t_clbk, 9-11, 15, 20, 21, 27, 29, 31, 34, 213,	torch::nn_selu(), <i>142</i>
215, 218, 221, 224, 224, 226, 227	torch::nn_sigmoid(), 144
t_clbk(), 20, 211	torch::nn_softmax(), 146
t_clbks (t_clbk), 224	torch::nn_softplus(), 147
t_loss, 10, 11, 21, 213, 215, 218, 221, 225,	<pre>torch::nn_softshrink(), 149</pre>
225, 227	torch::nn_softsign(), <i>151</i>
t_loss(), 20, 217	torch::nn_tanh(), <i>155</i>
t_losses (t_loss), 225	torch::nn_tanhshrink(), 156
t_opt, 10, 11, 20, 21, 213, 215, 218, 221, 225,	torch::nn_threshold(), 158
226, 226	torch::optimizer, 32, 34
t_opt(), 219	torch::sampler, 45, 185
t_opts (t_opt), 226	torch::torch_reshape(), 138
Task, 32, 33, 39, 46, 49, 164, 166, 167, 169,	torch::torch_squeeze(), 152, 208
172, 191, 202, 210, 216	torch::torch_unsqueeze(), 160 , 208
task, <i>199</i> , <i>200</i>	torch_callback, 9, 10, 15, 20, 27, 29, 31, 34,
task_dataset, 210	213, 221, 225
task_dataset(), 162	$torch_callback(), 13, 26$
tensor, 63, 211	torch_tensor, 16, 46, 164, 220
tensors, <i>166</i>	TorchCallback, 9-11, 13, 15, 20, 21, 25-27,
torch::dataloader, 32, 33, 46	29, 31, 34, 36, 38, 40, 42, 47, 48, 51,
torch::dataset, 15, 16, 46, 211	<i>52</i> , <i>173</i> , <i>211</i> , 211, <i>213</i> , <i>215</i> , <i>218</i> ,
torch::nn_batch_norm1d(), 72	221, 223–227
torch::nn_batch_norm2d(), 74	TorchDescriptor, 10, 11, 21, 213, 213, 218,
torch::nn_batch_norm3d(), 76	221, 225–227
torch::nn_celu(), 80	TorchIngressToken, 53, 64, 169, 174, 176,
torch::nn_conv1d(), 82	177, 179, 181, 202–206, 210, 216

```
TorchIngressToken(), 52
TorchLoss, 10, 11, 21, 36, 38, 40, 42, 47, 48,
        51, 52, 183, 202, 213, 215, 217, 221,
        225-227
TorchOptimizer, 10, 11, 21, 36, 38, 40, 42,
        47, 48, 51, 52, 191, 192, 202, 213,
        215, 218, 219, 225–227
torchvision::tiny_imagenet_dataset(),
torchvision::transform_adjust_brightness,
torchvision::transform_adjust_gamma,
torchvision::transform_adjust_hue, 194
torchvision::transform_adjust_saturation,
        194
torchvision::transform_center_crop, 54
torchvision::transform_color_jitter,
        54
torchvision::transform_crop, 55
torchvision::transform_grayscale, 195
torchvision::transform_hflip, 55
torchvision::transform_normalize, 196
torchvision::transform_pad, 196
torchvision::transform_random_affine,
torchvision::transform_random_choice,
        57
torchvision::transform_random_crop, 57
torchvision::transform_random_horizontal_flip,
torchvision::transform_random_order,
        58
torchvision::transform_random_resized_crop,
torchvision::transform_random_vertical_flip,
torchvision::transform_resize, 197
torchvision::transform_resized_crop,
torchvision::transform_rgb_to_grayscale,
torchvision::transform_rotate, 61
torchvision::transform_vflip, 61
```