

Package ‘adbcpostgresql’

April 15, 2024

Title 'Arrow' Database Connectivity ('ADBC') 'PostgreSQL' Driver

Version 0.11.0.1

Description Provides a developer-facing interface to the 'Arrow' Database Connectivity ('ADBC') 'PostgreSQL' driver for the purposes of building high-level database interfaces for users. 'ADBC' <<https://arrow.apache.org/adbc/>> is an API standard for database access libraries that uses 'Arrow' for result sets and query parameters.

License Apache License (>= 2)

Encoding UTF-8

RoxygenNote 7.2.3

SystemRequirements libpq

Suggests nanoarrow, testthat (>= 3.0.0)

Config/testthat/edition 3

Config/build/bootstrap TRUE

URL <https://github.com/apache/arrow-adbc>,
<https://arrow.apache.org/adbc/current/r/adbcpostgresql/>

BugReports <https://github.com/apache/arrow-adbc/issues>

Imports adbcdrivermanager

NeedsCompilation yes

Author Dewey Dunnington [aut, cre] (<<https://orcid.org/0000-0002-9415-4582>>),
Apache Arrow [aut, cph],
Apache Software Foundation [cph]

Maintainer Dewey Dunnington <dewey@dunnington.ca>

Repository CRAN

Date/Publication 2024-04-15 18:20:02 UTC

R topics documented:

| | |
|--------------------------|----------|
| adbcpostgresql | 2 |
| Index | 4 |

adbcpostgresql *ADBC PostgreSQL Driver*

Description

ADBC PostgreSQL Driver

Usage

```
adbcpostgresql()

## S3 method for class 'adbcpostgresql_driver_postgresql'
adbc_database_init(driver, ..., uri)

## S3 method for class 'adbcpostgresql_database'
adbc_connection_init(database, ..., adbc.connection.autocommit = NULL)

## S3 method for class 'adbcpostgresql_connection'
adbc_statement_init(
  connection,
  ...,
  adbc.ingest.target_table = NULL,
  adbc.ingest.mode = NULL
)
```

Arguments

| | |
|----------------------------|--|
| driver | An adbc_driver() . |
| ... | Driver-specific options. For the default method, these are named values that are converted to strings. |
| uri | A URI to a database path (e.g., postgresql://localhost:1234/postgres?user=user&password=pass). |
| database | An adbc_database . |
| adbc.connection.autocommit | Use FALSE to disable the default autocommit behaviour. |
| connection | An adbc_connection |
| adbc.ingest.target_table | The name of the target table for a bulk insert. |
| adbc.ingest.mode | Whether to create (the default) or append. |

Value

An [adbcdrivermanager::adbc_driver\(\)](#)

Examples

`adbcpostgresql()`

Index

`adbc_connection`, [2](#)
`adbc_connection_init.adbcpostgresql_database`
 (`adbcpostgresql`), [2](#)
`adbc_database`, [2](#)
`adbc_database_init.adbcpostgresql_driver_postgresql`
 (`adbcpostgresql`), [2](#)
`adbc_driver()`, [2](#)
`adbc_statement_init.adbcpostgresql_connection`
 (`adbcpostgresql`), [2](#)
`adbcdrivermanager::adbc_driver()`, [2](#)
`adbcpostgresql`, [2](#)